

BBik

STANDARDS DEVELOPMENT BRANCH OMIE



36936000007553

# **A PORTABLE COMPUTING SYSTEM FOR USE IN TOXIC GAS EMERGENCIES**

**FEBRUARY 1988**

**TD  
885.5  
.P678  
1988  
MOE**



**Ministry of  
Environment  
and Energy**

**TD**  
**885.5**  
**.P678**  
**1988**

A portable computing system  
for use in toxic gas emergencies  
/ Diamond, G.L; Tam, W.C;  
Misra, P.K; Sahota, H.

78813

Bbjk

ISBN 0-7743-8932-X

ISBN 0-7729-3448-7 (Rev. Ed.)

**A PORTABLE COMPUTING SYSTEM  
FOR USE IN TOXIC GAS EMERGENCIES**

**G.L. Diamond, W.C. Tam, P.K. Misra, and H. Sahota**

**Ontario Ministry of the Environment  
Air Resources Branch  
880 Bay Street, 4th floor  
Toronto, Ontario M5S 1Z8**

**February 1988**

**ARB-150-87**

2 25-1987  
PDB library

### Copyright Provisions and Restrictions on Copying:

This Ontario Ministry of the Environment work is protected by Crown copyright (unless otherwise indicated), which is held by the Queen's Printer for Ontario. It may be reproduced for non-commercial purposes if credit is given and Crown copyright is acknowledged.

It may not be reproduced, in all or in part, part, for any commercial purpose except under a licence from the Queen's Printer for Ontario.

For information on reproducing Government of Ontario works, please contact Service Ontario Publications at [copyright@ontario.ca](mailto:copyright@ontario.ca)



**PORTABLE COMPUTING SYSTEM FOR**

**USE IN TOXIC GAS EMERGENCIES**

## **DISCLAIMER**

This report has been prepared by the Air Resources Branch of the Ministry of the Environment on the basis of work performed internally, work by consultants, and published work in scientific literature. All reasonable care has been taken, but the Ministry cannot absolutely guarantee the accuracy or applicability to any given situation of this report or the computer programs described herein.

The Ministry of the Environment takes no responsibility whatsoever for any outcome resulting from use of this report or computer program.

## SUMMARY

This report serves as the documentation for the Portable Computing System for Use in Toxic Gas Emergencies. This system, developed and maintained by the Special Studies and Research Management Unit of the Air Resources Branch, has three main objectives:

- a) to provide hazardous contaminant and dispersion modelling information quickly in an emergency;
- b) to be "user friendly" to all users; and
- c) to be easily transportable so that it can be used at home or at emergency sites.

The report is written in modules so that readers of different sophistication in computer modelling of toxic gas dispersion can use different parts of it. Chapter 1 details the rationale for developing the system and the scope of its intended use. Chapter 2 provides some background information on the modelling calculations and the information sub-system. Chapter 3 is a user's manual, giving step-by-step instructions for use of the system. Chapter 4 contains flow charts showing the system design as well as the data structure of the files making up the information sub-system.

The programs and further documentation can be obtained from:

Air Resources Branch  
Ontario Ministry of the Environment  
880 Bay Street, 4th Floor  
Toronto, Ontario, Canada  
M5S 1Z8  
Attention: Dr. Gerald Diamond  
Phone: (416) 965-4081

# PORTABLE COMPUTING SYSTEM FOR USE IN TOXIC GAS EMERGENCIES

## TABLE OF CONTENTS

### CHAPTER 1: INTRODUCTION

### CHAPTER 2: BACKGROUND

- 2.1 FORMATION OF HAZARDOUS VAPOUR CLOUDS
- 2.2 DISPERSION MODELS
- 2.3 SOURCE STRENGTHS
- 2.4 SIMPLE GAS MODEL
- 2.5 HEAVY GAS MODEL
- 2.6 INFORMATION SYSTEM
- 2.7 SYSTEM OUTPUT

### CHAPTER 3: USER'S MANUAL

- 3.1 INFORMATION SYSTEM
- 3.2 GAS SYSTEM
- 3.3 INFORMATION SYSTEM
- 3.4 SIMPLE GAS MODEL
- 3.5 HEAVY GAS MODEL
- 3.6 METINFO

### CHAPTER 4: PROGRAMS

- 4.1 SYSTEM DESIGN & FLOW CHARTS
- 4.2 FILE STRUCTURES FOR THE INFORMATION SYSTEM

### APPENDIX:

- I. SYNONYM TABLE
- II. FILE HAZARD CODE
- III. REFERENCES
- IV. DATA SOURCES

## **CHAPTER 1: INTRODUCTION**

## 1. INTRODUCTION

The extensive use of hazardous gases in our industrial society results in significant storage, handling and transportation problems. Toxic gases such as ammonia, chlorine and hydrogen sulphide are stored in refrigerated vessels or pressurized tanks and are transported by ship, truck, and train.

The manufacturers and shippers of these materials do their best to ensure that the materials are stored and moved safely and that hazards due to toxic properties of these materials are minimized. Failure of various elements of these systems, however, can sometimes disrupt our lives. In Toronto and Mississauga, a train derailment in 1979 caused a quarter of a million people to be evacuated and police, firefighters, meteorologists, hospital staff, ambulance crews, and environmental scientists all played critical roles in handling the emergency. A train derailment at Medonte, near Barrie, Ontario, in 1982 threatened the surrounding community with the potential rupture of a tank car containing 39 tons of anhydrous hydrogen fluoride. In other countries lives have been lost in such accidents.

In 1980, the Ontario Ministry of the Environment began development of computerized dispersion models on an IBM mainframe computer to estimate the concentration of toxic gases resulting from unusual releases to the atmosphere. The models can be used to help in decision-making about evacuation in the general area of an accident. When major emergencies occur outside usual business hours (as often happens), these programs can be run on a terminal from the home of MOE staff via telephone line. Since the user requires his phone line to run these models, however, his communication line is cut off. As well, if the mainframe is down for maintenance or for some other reason, these models cannot be used.

To avoid such situations, the Ministry of the Environment has adapted the Simple Gas Model and the Heavy Gas Model to a portable computer (IBM PC). The resulting system also contains useful information on

certain priority chemicals which might be involved in emergencies in Ontario. A portable computer can be brought to the emergency site and used there. If kept in the homes of personnel on a rota basis, it can also be used to provide a fast information response when major emergencies occur outside normal office hours.

This Portable Computing System for Use in Toxic Gas Emergencies (henceforth referred to as the GAS SYSTEM) is designed to be very user-friendly so that a minimum of computer competency is required to run it. It is not meant to replace the more sophisticated mainframe models. Rather, its main purpose is to provide fast, first-cut information to advise appropriate emergency handling authorities at the emergency site. The system will provide hazardous contaminants information, calculate toxic gas concentrations at different distances downwind of an emergency site, and display this information graphically against important marker levels such as TLV, STEL and IDLH values (Threshold Limit Values; Short Term Exposure Limits; Immediately Dangerous to Life or Health). This information will aid authorities in decision making about evacuation of people in the general area of the emergency. Meanwhile, professional modellers from industry and government can set up more detailed models for the particular circumstances.

## **CHAPTER 2: BACKGROUND**



## 2.1 FORMATION OF HAZARDOUS VAPOUR CLOUDS

The accidental escape of chemicals during manufacture, storage, and transportation can harm the public. The understanding of the atmospheric dispersion of toxic vapours is, therefore, an essential element in chemical safety plans. One of the most important properties of such vapours is that many of them are denser than air. Many other vapours, although not normally denser than air, may become so under typical emergency conditions. Following are some examples of denser-than-air behaviour for gases that, at first sight, should be buoyant. This is important because such gases will tend to remain near the ground while moving downwind, thus increasing the risk in the downwind area.

Gases can be intrinsically dense because their molecular weight exceeds that of air. Chlorine is an example of a dense toxic vapour. The petrochemical industry produces and transports a range of flammable dense hydrocarbons such as propane, butane, and propylene. Although methane is a gas whose molecular weight is less than that of air, it is dense if released at its boiling point of  $-161^{\circ}\text{C}$ . Natural gas is often stored or transported as liquid and a cold, dense vapour can be generated if liquified natural gas should be spilled onto land or water.

A superficially surprising example of a gas that can form a denser than air mixture is ammonia, which is chemically toxic. Its molecular weight is only 17 and, at its boiling point of  $-33^{\circ}\text{C}$ , the vapour is less dense than air at  $20^{\circ}\text{C}$ . Nonetheless, there are several examples of accidental releases of ammonia from pressurized containers in which the resulting gas cloud was denser than air (Kaiser and Walker, 1978), or at least non-buoyant. The reason for this is as follows. If ammonia is kept as a liquid at the ambient temperature, it is under considerable pressure. If the vessel containing the ammonia should fail, there is an immediate bulk boiling of the liquid. About twenty per cent of its mass can typically vaporize, with the heat supplied by cooling the remaining ammonia to its boiling point. The vigour of the bulk boiling process can throw most, if not all, of the remaining liquid into the

air as a fine aerosol. At the same time, air is entrained. This air supplies heat to evaporate the ammonia droplets so that a mixture of air and ammonia, possibly at the boiling point of ammonia, is formed. Such a mixture can be denser than the surrounding air, if the circumstances favour the release of a substantial percentage of the ammonia as fine liquid droplets. Such a case occurred in the USA in May, 1976. Nineteen tons of anhydrous ammonia were released in a dense cloud in suburban Houston when a tanker truck crashed through a barrier on an elevated expressway.

Another example is hydrogen fluoride, a toxic gas used by the nuclear industry during the fuel manufacturing process, and by the chemical industry as a catalyst in alkylation plants. Its molecular weight is normally 20, but as a pure vapour it is highly associated and consists of a mixture of a hexamer and monomer with an effective molecular weight of about 70. Disassociation takes place as the hydrogen fluoride is diluted with air, but the heat required to do this is extracted from the mixture and tends to keep it denser than the surrounding air. However, there is no known example of a large scale accidental release in which this density effect has been observed.

From the foregoing examples, it is apparent that a knowledge of the way in which "heavy" toxic vapours disperse in the atmosphere is essential to analyse the potential risk in accidents involving toxic chemicals.

## 2.2 DISPERSION MODELS

After the release of a toxic vapour, its concentration at different distances downwind can be estimated using dispersion models. The purpose of the dispersion calculations presented in this portable computing system is to obtain a rough estimate of the dispersion of hazardous vapour. Various simplifying assumptions are incorporated into models of different sophistication. The reader should be aware of the inherent assumptions and the limits of applicability of these models. Otherwise, gross misinterpretation of the implications of a particular situation may result. For instance, the terrain is assumed

to be flat. In a real situation, channelling due to buildings or valleys can lead to higher concentrations than predicted.

The accidents dealt with can be subdivided into two major types:

a) Continuous Release (Plume Formation) - A leak occurs in a gas container or above the liquid level in a liquid container.

Alternatively, liquid is released, forms a pool and evaporation causes vapour release to the atmosphere.

b) Instantaneous Release (Puff Formation) - This is the release of a large amount of gas in a very short time (in the order of seconds to minutes). A major rupture in a container of a highly volatile chemical can cause such a release, e.g. a BLEVE (Boiling Liquid Expanding Vapour Explosion).

Two types of dispersion model have been incorporated in the present system. The Simple Gas Model can deal with either a continuous or instantaneous release and uses different equations to estimate the concentration downwind for these two situations. The Heavy Gas Model, although a more mathematically sophisticated model, can only deal with instantaneous releases in our system. It will give a more realistic representation of an instantaneous heavy gas release.

### 2.3 SOURCE STRENGTHS

The use of these models requires that the amount of gas released (i.e. source strength) be known. Source strengths can be estimated using basic principles of thermodynamics and fluid mechanics. In the development of the following formulae, gases are assumed to behave ideally and the venting process is assumed to be isothermal. Equilibrium thermodynamics, although not strictly applicable, is employed for simplicity. These assumptions may not be valid in many cases, but they do give a worst-case scenario.

### 2.3.1 Gas Release

Gas will be released when the hole in the tank is above the liquid level. The maximum limiting flow rate for gas release is during "choked" flow. This flow rate is

$$q_v = C_d A P \sqrt{\left[ \frac{KM}{RT} \right] \left[ \frac{2}{K+1} \right]^{\frac{K+1}{K-1}}}$$

where  $q_v$  = vapour venting rate  
 $T$  = absolute temperature in the tank  
 $M$  = molecular weight  
 $R$  = universal gas constant  
 $P$  = tank pressure  
 $K$  = specific heat ratio for the vapour  
 $C_d$  = coefficient of discharge  
 $A$  = area of rupture

The criterion for choked flow is

$$\frac{P}{P_a} > \left[ \frac{K+1}{2} \right]^{\frac{K}{K-1}}$$

where  $P_a$  = atmospheric pressure.

For unchoked flow,

$$\frac{P}{P_a} \leq \left[ \frac{K+1}{2} \right]^{\frac{K}{K-1}}$$

and the flow rate becomes

$$q_v = C_d A \sqrt{2P\rho_v \left[ \frac{K}{K-1} \right] \left\{ \left[ \frac{P_a}{P} \right]^{\frac{2}{K}} - \left[ \frac{P_a}{P} \right]^{\frac{K+1}{K}} \right\}}$$

where  $\rho_v$  = density of vapour.

### 2.3.2 Liquid Release

Liquid is released when the hole in the tank is below the liquid level. Then,

$$q_l = C_d A \rho_l \sqrt{2gH + \frac{2(P-P_a)}{\rho_l}}$$

where  $q_l$  = instantaneous liquid venting rate  
 $H$  = height of liquid column above hole  
 $P$  = tank pressure  
 $A$  = area of rupture  
 $C_d$  = coefficient of discharge  
 $\rho_l$  = density of liquid  
 $g$  = acceleration due to gravity  
 $P_a$  = atmospheric pressure

Stiver and MacKay (1982) give the evaporation rate for chemicals that form a liquid pool when spilled on a ground or water surface as:


$$Q = \frac{K_m A P M}{RT}$$

where  $Q$  = evaporation rate (vapour release rate), kg/s  
 $K_m$  = mass transfer coefficient, m/s  
 $A_p$  = pool area, m<sup>2</sup>  
 $P$  = vapour pressure, Pascal (i.e. N/m<sup>2</sup>)  
 $M$  = molecular weight  
 $R$  = gas constant, 8.314 (Pa)(m<sup>3</sup>)/(mole)(°K)  
 $T$  = temperature, °K

At a temperature of 20°C, the evaporation rate can be given numerically as

$$Q = 8.5 \times 10^{-10} A_p P M u^{0.78} \text{ kg/s}$$

where  $u$  = the wind speed in m/s.



The evaporation rates at temperatures other than 20°C use the following equation:

$$Q_t = Q_{20^\circ\text{C}} \times \frac{P_t}{P_{20^\circ\text{C}}} \times \frac{T_{20^\circ\text{C}}}{T_t}$$

where the subscript t denotes the temperature at which the evaporation rate is desired.

The accompanying flow chart shows how the computer program determines the release rate of toxic gases in an accident.

#### 2.4 SIMPLE GAS MODEL


This model is essentially a simplified mathematical description of the physical behaviour of the released gas. In its simplest form, the model expresses the mass balance of the released gas.

In using the puff and plume equations described below, the following assumptions have to be noted (from TIPS Manual, Environment Canada):

- a) The vapour that is diffusing is neutrally buoyant; that is, there is no gross movement of the vapour cloud caused by either gravity or buoyancy.
- b) Mixing with air is uniform throughout the vapour cloud.
- c) The concentration obtained is time-averaged.
- d) The wind is uniform throughout the vertical extent of the cloud.
- e) The terrain is assumed flat (i.e. no terrain effects).
- f) No depletion of the puff/plume (e.g. by deposition).

#### 2.4.1 Continuous Release Case (Plume), Simple Gas Model

Consider a continuous release of gas at a rate of  $Q$  at ground level. Plume behaviour can be simplified as a half-pyramid with the apex at the source. Figure 1 illustrates this.



$u$  : MEAN WIND SPEED  
 $x$  : DOWN WIND DISTANCE FROM THE SOURCE  
 $\sigma_z$  : VERTICAL FLUCTUATION  
 $\sigma_y$  : HORIZONTAL FLUCTUATION

FIGURE 1

If we consider the shaded cross-section, the conservation of matter can be stated as

$$Q = 2\sigma_y \sigma_z x u C \quad (1)$$

where  $C$  is the concentration of the gas at distance  $x$ . Formula (1) can be rewritten as

$$C = \frac{Q}{2\sigma_y \sigma_z x u} \quad (2)$$

We can see that:

(a) the concentration is directly proportional to the emission rate  $Q$ ;



- (b) the concentration is inversely proportional to the wind speed  $u$ ;  
and
- (c) the concentration falls approximately as  $x^2$ .

The height of the plume in the atmosphere cannot exceed the mixing layer height,  $z$ . When the plume height reaches  $z$ , the plume will spread horizontally only, instead of both horizontally and vertically as shown in Figure 2.




FIGURE 2

Equation (2) now becomes

$$C = \frac{Q}{2\sigma_\theta x \sigma_z u}, \quad z < \sigma_\theta x \quad (3a)$$

$$C = \frac{Q}{2\sigma_\theta x z u}, \quad z \geq \sigma_\theta x \quad (3b)$$

Using equations (3a) and (3b), the maximum permissible emission rate or

a caution distance can be calculated, provided that the critical concentration is known.

#### 2.4.2 Instantaneous Release Case (Puff), Simple Gas Model

In the simple gas model, instantaneous release is considered as a puff release. That is, all the material released is assumed to be contained within an ellipsoidal puff (Fig. 3) and the distribution of the toxic gas within the puff is assumed to be Gaussian. Parameters 'a', 'b' and 'c' define the major and minor axes of the puff. As the puff moves downwind, it increases in size. Equation 4 gives the new value of the major and minor axes of the puff as it moves downwind.

Equation 4a gives the concentration within the puff.

Since the material in the puff cannot escape the capping inversion, when the vertical axis 'c' of the puff exceeds the mixed layer height, it is set equal to this height; i.e.,  $c = z$ . Equation 4b then gives the concentration within the puff.

Then conservation of mass requires that

$$C = \frac{2W}{(2\pi)^{3/2}(\sigma_{\theta x})^2\sigma_{\phi x}}, \quad \sigma_{\phi x} < z \quad (4a)$$

$$C = \frac{2W}{(2\pi)^{3/2}(\sigma_{\theta x})^2 z}, \quad \sigma_{\phi x} \geq z \quad (4b)$$

where C is the concentration of the gas at the centre of the puff and z is the mixing layer height.




FIGURE 3

The time of exposure to the puff at a distance  $x$  downwind from the source is the time taken for the ellipsoid to pass that point.

$$\text{Time of exposure} = \frac{8\sigma_y x}{u} \quad (5)$$

If a critical concentration is given, equations (4a) and (4b) can be reversed to calculate a caution distance.

## 2.5 HEAVY GAS MODEL

In the present system, the heavy gas model can only be used for instantaneous releases. In some cases the hazardous gas is released in a very short time interval (i.e. practically instantaneous). Chlorine escaping suddenly from a fractured pressured vessel is a typical example. The gas appears in the form of a cloud which drifts downwind as it disperses. Figure 4 shows a schematic of a dispersing puff.




FIGURE 4

### 2.5.1 Cloud Formation

The fraction,  $\delta$ , of the liquid mass thrown into the air-gas mixture as droplets during the release, evaporates. Depending upon the type of gas and release, this fraction may vary from almost zero to close to one. A typical value is 0.8 (Kaiser and Walker, 1978). The temperature of the cloud will not rise much until enough warm air has been entrained to evaporate the droplets. The necessary amount of entrained air is

$$M_{ad} = \frac{\delta M_g L_g}{C_{pa}(T_a - T_g) + L_w X_w} \quad (6)$$

Here  $X_w$  is the mixing ratio of water vapour,  $L_w$  is the latent heat of evaporation or sublimation of water,  $M_g$  is the mass of the released gas, and  $L_g$  is the latent heat of the gas (K.J. Eidsvik, 1979).  $C_{pa}$  is the heat capacity (1005.7 J/kg) of air, which will be cooled during the evaporation process from ambient temperature  $T_a$  to  $T_g$ , usually the boiling point of the gas.

**Ontario Ministry of the Environment, Air Resources Branch**

**INSTRUCTIONS FOR INSTALLING AND RUNNING  
EMERGENCY RESPONSE PROGRAM, MAY 1990 VERSION**

**INTRODUCTION:**

The Emergency Response Program (ERP) resides on 3 installation diskettes. Please follow the steps listed below carefully.

If you are attempting to install ERP on a hard disk that already contains a previous version of ERP, delete the previous version prior to installation (i.e. delete the files and subdirectories in C:\ERP). Prior to deleting these files, back up any output files on C:\ERP that you may have produced while running the previous version of ERP.

If a mistake is made during installation, delete the files and subdirectories in C:\ERP and start over.

**SYSTEM REQUIREMENTS:**

One 5.25" Floppy Disk Drive as Drive A (360K or 1.2 megabytes)  
One Hard Disk Drive (minimum 10 megabytes)  
IBM XT/AT/386/486 or compatible system  
DOS 2.0 or later version  
Math coprocessor recommended, but not required

**INSTALLATION:**

The installation is performed on the C drive. Place Installation Diskette #1 in drive A and type:

**A:\INSTALL**

to begin the installation. Then follow the instructions as they appear. You will be prompted to insert the 3 diskettes in sequence.

**RUNNING ERP:**

After installation, you may run ERP. To run the program go to directory C:\ERP and execute the batch file AUTOEXEC. To do this, type:

```
C:           , then
CD \ERP      , then
AUTOEXEC
```

to run ERP.

The first module to be executed is **METINFO**. This module allows for the inputting of meteorology, source and receptor information. It should be noted that NOT ALL INFORMATION ASKED FOR IN THIS MODULE IS USED BY EVERY PROGRAM. For example, receptor and stack information is not used by the HEAVY GAS model. In addition, please note that the use of a unit emission rate (i.e. 1.0 grams/second) may be desired since this may make computations easier for multiple scenarios. To allow for the actual emission rate, simply multiply the final concentration by the actual emission rate. For example, if the final concentration at a given receptor is 1.22 ug/m\*\*3 and the actual emission rate is 2 grams/second, multiply the two figures to get 2.44 ug/m\*\*3. (For those concerned about unit conversions, note that using a unit emission rate implies that the units of concentration are actually (ug/m\*\*3)/(g/s).)

#### **SELECTING THE MODEL:**

After the meteorology, source and receptor information is entered, a model menu is displayed (which you can enter directly from **METINFO** by typing C, for Continue). Enter the model which is to be run. The program will then branch to the chosen model and begin execution. There are some specific inputs required within the individual models. You will be prompted for any further information required by the model. Note that when a program is expecting input from the keyboard, you CANNOT terminate it. The only way to get out of the situation is by entering the required information or by rebooting (i.e. by simultaneously pressing the ALT, CNTL and DEL keys).

#### **HEAVY and SIMPLE GAS MODELS:**

To run the Heavy Gas or Simple Gas models, you must select a specific chemical from the chemical list. Follow the instructions as they appear on the screen. The Heavy Gas model contains two very important inputs: The **Amount of Gas Released** and the **Initial Radius of the Cloud**.

#### **PROPOSED REGULATION 308 MODEL:**

The Proposed Regulation 308 model requires as input meteorology, source and receptor data (inputted through **METINFO**, as described above). There are a variety of optional inputs that you may choose to enter. Each requires that a special code be used in place of a source parameter. These optional inputs and codes are summarized in the following table:

| Optional Input Required<br>----- | Code Source Parameter to Use<br>----- |
|----------------------------------|---------------------------------------|
| Buoyancy Flux                    | -888 Stack Temperature                |
| Momentum Flux                    | -888 Stack Exit Velocity              |
| Initial Vertical Plume Height    | -888 Building Height                  |
| Initial Horizontal Plume Width   | -888 Building Width                   |
| Stack Temperature to Ambient     | -999 Stack Temperature                |

If, for example, you wish to input you own buoyancy flux (as, for example, in a flare situation) then you must input **-888.0** for the stack temperature. This (clearly impossible) temperature is a code that indicates to the model that the buoyancy flux will be inputted by you, not calculated by the model. You will then be asked to enter the buoyancy flux when you run the model.

After the optional inputs have been entered, you will be asked for an output filename. If you wish the output to appear on the screen simply press **<enter>**. Otherwise, enter the filename. Please note that the filename should be a simple filename, with no path specified. If the file already exists, it will be overwritten. To view the file, exit **ERP** (i.e. go to **DOS**) and use the **TYPE** command. The file will be found in the directory **C:\ERP**.

#### **SOURCE CODE:**

Unlike some previous version of **ERP**, the source code is not automatically installed on the C drive. In order to retrieve the source code, place Installation Diskette #3 in Drive A and type:

**A:\GETCODE**

The source code will be automatically installed in **C:\ERP\SCODE**. Note that the source code must be decompressed, so installation will take a few minutes. Note that the BASIC programs are written in Microsoft QuickBASIC V4.5 and the FORTRAN programs are written in Microsoft FORTRAN V4.1. Batch files to aid in compilation and linking are included.

If you have any questions about installing or running **ERP**, please contact Mr. H. Sahota at 416-235-5764.

-----  
IBM is a registered trademark of International Business Machines Corporation.

Microsoft is a registered trademark of Microsoft Corporation.

Since the mass of air entrained is assumed to be ten or twenty times that of the gas in the escaping puff, the law of conservation of momentum dictates that the initial velocity is roughly that of the surrounding air. The puff is assumed to move with the wind speed (measured at a height of 10 m).

### 2.5.2 Slumping

The initial spreading of the dense cloud resulting from a heavy gas release is controlled by gravitational effects. The cloud essentially slumps under the influence of gravity. To analyze this behaviour, we have followed Kaiser and Walker (1978) and assumed that the cloud is in the form of a cylinder with radius  $r$  and height  $h$ . The velocity of the edge of the cloud is adequately described by the liquid column analogy:

$$\frac{dr}{dt} = C \left[ \frac{(\rho - \rho_a)}{\rho} gh \right]^{\frac{1}{2}} = \frac{C}{r} \left[ \frac{(\rho - \rho_a) g V_o}{\pi \rho} \right]^{\frac{1}{2}} \quad (7)$$

where  $dr/dt$  is the spreading velocity of the cylinder of heavy gas,  $\rho$  is the density of the gas-air mixture in the cloud,  $\rho_a$  is the density of the surrounding air ( $1.2 \text{ kg/m}^3$  at  $20^\circ\text{C}$ ), and  $C$  is a constant. Van Ulden (1974) suggested  $C = 1$  as the constant with his field experimental results. We have also assumed that the volume and the concentration of the cloud remains approximately constant, at  $V_o$  and  $C_o$  respectively, as the cloud slumps. Integrating equation (7) gives

$$r^2 = r_o^2 + 2 \left[ \frac{(\rho - \rho_a) g V_o}{\pi \rho} \right]^{\frac{1}{2}} t \quad (8a)$$

$$\frac{dr}{dt} = \frac{1}{r} \left[ \frac{(\rho - \rho_a) g V_o}{\pi \rho} \right]^{\frac{1}{2}} \quad (8b)$$

$$C_o = \frac{M}{V_o} \quad (8c)$$



Since the concentration remains essentially unchanged at its initial value throughout the slumping phase, exposure levels could be exceedingly high at distances of the order of a few kilometers from the release site.

### 2.5.3 Termination of Slumping

Slumping is terminated by entrainment of air. This results in a dense cloud which hugs the ground as it travels downwind while the height of the cloud begins to grow slowly. Sooner or later the cloud or dispersing gas must become so dilute that atmospheric turbulence becomes dominant in controlling cloud growth. Van Ulden (1974) recommends as a criterion for the end of the slumping phase setting the turbulence energy density equal to the mean potential energy density; that is to say

$$\frac{1}{2} (\rho - \rho_a) gh = 2\rho u_*^2 \quad (9)$$

Here  $u_*$  is the friction velocity due to mechanical turbulence and is related to the mean wind speed  $u$  by  $u_* = cu$ , where  $c$  is a "surface drag constant" that depends on the weather category.

Applying equation (7), this criterion is equivalent to

$$\left[ \frac{(\rho - \rho_a) gh}{\rho} \right]^{\frac{1}{2}} = \frac{dr}{dt} = 2u_* \quad (10)$$

Combining equations (8b) and (10), the radius at the end of the slumping phase can be shown to be

$$r_T = \frac{D}{2u_*} \quad \text{where } D = \left[ \frac{(\rho - \rho_a) g V_o}{\pi \rho} \right]^{\frac{1}{2}} \quad (11)$$

Then the duration of the slumping phase is given by equation (8a) as

$$t_T = \frac{r_T^2 - r_o^2}{2D} \quad (12)$$

After  $t = t_T$ ,  $dr/dt$  becomes independent of  $r$ . To be consistent with equation (10),  $dr/dt = 2u_*$  and

$$r = r_T + 2u_*(t - t_T) \quad (13)$$

Similarly, for the growth of cloud height, Eidsvik gives

$$h = h_T + \alpha u_*(t - t_T) \quad \text{for } h < z \quad (14)$$

where  $\alpha$  is a coefficient for vertical entrainment with a value of about 0.4.

## 2.6 INFORMATION SYSTEM

In addition to the source strength programs and modelling programs the computer contains an information sub-system. This sub-system contains physical and chemical data on priority chemicals. In a previous MOE report "Atmospheric Monitoring for Transportation Emergencies" (ARB-030-81), 79 of these chemicals were identified as posing the highest risk to human health and the environment from transportation-related spills in Ontario. Since that time, more chemicals which could possibly pose a threat to the citizens of Ontario have been added. These chemicals were selected by considering the inherent toxicity of the chemical or its products, and the probability of its being involved in a spill in Ontario.

For each chemical, the following physical and chemical data, where available, are stored in retrievable form:

- i) Formula
- ii) Molecular weight
- iii) Latent Heat of Vapourization (or Sublimation)
- iv) Boiling Point - measured at 1 atmosphere
- v) Solubility - measured at 0°C unless specified inside brackets
- vi) Specific Gravity - with respect to 4°C water at 1.00. (If gaseous, the value reported is that of the liquid in a common compressed state.)
- vii) Vapour Pressure - saturated vapour pressure measured at 20°C unless otherwise specified inside brackets
- viii) Vapour Density - with respect to air at 1.00.

- ix) Flash Point - measurement method coded inside brackets  
(CC) closed cup method  
(OC) open cup method
- x) IDLH - Immediately Dangerous to Life and Health concentration  
This is usually defined as a thirty minute exposure. It is used as a guide in the industrial situation as a concentration from which workers would not be able to safely escape if their respiratory equipment failed.
- xi) TLV - Threshold Limit Values (Time Weighted Average)  
This is defined as the time weighted average concentration for a normal 8-hour workday and a 40-hour workweek, to which nearly all workers may be repeatedly exposed, day after day, without adverse effect.
- xii) STEL - Short Term Exposure Limit  
This is defined as a 15-minute time-weighted average exposure which should not be exceeded at any time during a workday even if the eight-hour time-weighted average is within the TLV.
- xiii) Specific Heat Ratio - ratio of specific heats of the vapour at constant pressure and at constant volume
- xiv) Synonyms - different names for the same chemical
- xv) Fire Hazards Code - describes the flammability or combustibility of the chemical and any special hazards posed by its combustion or behaviour in a fire, including toxic products or potential for explosion.

## 2.7 SYSTEM OUTPUT

The output from the information sub-system is combined with the model calculations to give useful information on potential concentrations of toxic gases downwind of a release. If a critical concentration for human health is entered into the system, a "caution distance" will be calculated. If actual measurements of toxic gas concentrations are made at the site, an emission rate may be estimated.

The Simple Gas Model output can be graphically displayed on the computer terminal, showing downwind concentration in context with TLV and IDLH levels (Threshold Limit Values and Immediately Dangerous to Life and Health values).

The Heavy Gas Model output can be printed on a portable printer, and this output is given for a series of different downwind distances. In addition, it may be plotted if a plotter is available.

### **CHAPTER 3: USER'S MANUAL**

### 3.1 INFORMATION SYSTEM:

#### 3.1.1 Requirements

The Emergency response program models are implemented on an IBM/PC\* compatible system. Minimum system requirements in addition to the basic system are two 5 $\frac{1}{4}$ " disk drives, 640 kilobytes of memory (total), printer and plotter (if plots with better resolution of the output are required). A math co-processor 8087 or 80287 (for AT compatible systems) is advantageous since it reduces the execution time of the programs.

When the system is initially booted (started) the Gas System Menu will appear. Before any model is selected, the user MUST select the chemical which he wants to model from the Information System. After the chemical is selected (if the desired chemical is not in the list then there is provision for adding the chemical name and the associated properties), the user selects which of the gas models he wants to run. The use of GAS SYSTEM MENU, INFORMATION SYSTEM, SIMPLE GAS MODEL and the HEAVY GAS MODEL are described in section 3.3, 3.4, 3.5 and 3.6 respectively.

It is strongly recommended that the user make a copy of the disks before using them for the first time.

#### 3.1.2 Disk Drive Operations

The IBM PC generally has two disk drives. Usually the one on the top or on the left is called drive A and the one on the right or bottom is drive B.

---

**\*NOTE:** These computers generate and use radio frequency energy, and if not installed and used properly may cause interference to radio reception.

Please note the following:

1. NEVER ATTEMPT TO REMOVE A DISKETTE from a drive while the disk activity light is on.
2. It is very easy to damage a diskette's surface and lose the information stored on it.
3. Avoid placing the diskette near any magnetic field (this erases all the information).
4. Keep all exposed surfaces protected from dust and contact with other foreign materials. Keep the diskette inside its paper envelope unless it is being used in the drive.
5. Store diskette in a cool, clean, dry place.
6. Do not touch the magnetic surface with your fingers.

### 3.2 GAS SYSTEM

#### 3.2.1 Set Up Procedure

GAS SYSTEM consists of several basic programs and some data files. They are stored on the diskette. To start the system, follow this procedure.

- 1) Turn your computer on. Follow your normal start-up procedures.
- 2) Insert Disk A into Drive A and Disk B into Drive B.
- 3) Type A: (return) if you are not on Drive A.

- 4) Type Autoexec (return).

\*\*\*\*\* WARNING \*\*\*\*\*

This program may not run on all basic interpreters or compilers.

\*\*\*\*\*

- 5) A disclaimer should appear on your screen. You should read it carefully the first time you use the program.
- 6) Press any key after reading the disclaimer and a menu like the one depicted below should appear.

```
*****  
* GAS SYSTEM MENU *  
*****
```

1. FOR INFORMATION ACCESS
2. FOR SOURCE STRENGTH EST.
3. FOR METINFO.
4. FOR SIMPLE GAS MODEL
5. FOR HEAVY GAS MODEL
6. EXIT


SELECT →

- 7) Pressing (1)\* will give you access to the information system. If you do not run this now, you will be using parameters for whatever gas was modelled by the previous user of the program.
- 8) Follow the instructions in the succeeding sections to run the various programs.
- 9) When finished and the GAS SYSTEM MENU appears on the screen, press 6 to exit. Type "system" to exit most Basic interpreters.
- 10) Remove the diskettes from the computer and place them in their envelopes.

### 3.2.2 Normal Operation Steps in Case of Emergency

- 1) Run the information Sub-system to look for the chemical in question. The system will store the properties of the located chemical in a data file (JINFO.DAT) for later reference by the models. If the chemical is not in the list, consult other emergency response handbooks. New chemicals may easily be added to your list.
- 2) If you do not know the source strength, press (2) at the Gas System menu and an estimation program will enable you to determine an approximate value.

---

\*Note: Single keystrokes will be denoted by a character or phrase inside brackets. Thus (1) indicates the computer key with 1 on it - a lower case L will not be interpreted by the computer as a 1. (Return) is the key near the right hand side of the computer which may be marked RETURN, or ENTER, or with a small arrow such as .

Upper case letters indicate the letter in question while lower case letters are variables which in general stand for a number.



- 3) Run the Simple Gas Model. If you have run the source strength routine, the computer will use the value as a default.
- 4) If the release is instantaneous and time permits you can run the heavy gas model to obtain a more realistic estimate of downwind concentrations.

NOTE: If you are going to run the heavy gas model, you must run the **Metinfo** system first.

### 3.3 INFORMATION SYSTEM

The Information System consists of a set of programs and files (See Chapter 4) to provide information on physical and chemical properties of various hazardous chemicals. The system consists of 5 routines:

the Display Routine,  
the Add Routine,  
the Delete Routine,  
the Modify Routine, and  
the Change Routine.

The DISPLAY ROUTINE finds and exhibits selected physical and chemical properties, synonyms, and fire hazard codes of the requested chemical compound if it is in the Information File.

The ADD ROUTINE is used to put a new chemical compound into the Information File. The user must provide all information in standard units displayed.

The DELETE ROUTINE removes an entire gas record from the information system, together with all its synonyms. EXTREME CAUTION should be exercised with this.

The MODIFY ROUTINE allows the user to add physical or chemical properties to all the records in the Information File.

The CHANGE ROUTINE allows a user to alter the value of one or more fields of the requested chemical; or to put in the value of a new field added by the MODIFY ROUTINE.

\*\*\*\*\* WARNING \*\*\*\*\*

Take extreme care while running the ADD, DELETE and MODIFY routines. They alter the file structure and mistakes cannot be easily undone.

\*\*\*\*\*

### 3.3.1 Getting Into Routines

After pressing (1) at the GAS SYSTEM MENU and shortly after a "PLEASE WAIT A MINUTE" message is displayed, the Main Selections Display for the Information Sub-system will appear as below:

\*\*\*\*\*

\* INFORMATION ACCESS \*

\*\*\*\*\*

1. DISPLAY    INFORMATION ON SPECIFIED CHEMICAL
2. ADD        ADD NEW CHEMICAL
3. MODIFY    ADD NEW PROPERTY
4. HELP      HOW TO USE THIS PROGRAM
5. EXIT      TO GAS SYSTEM MENU

SELECT -->

To get into the DISPLAY ROUTINE, type (1) and press the RETURN key.

You will then be offered the choice of two ways of finding the chemical you wish to model. Pressing (1) allows you to scan the entire list in pages of 20 chemicals (see next section). Pressing (2) will cause the prompt "ENTER KEYWORD OF CHEMICAL:" to appear. You may then type in the chemical name (or part of a name). The computer will then scan the list of chemicals and synonyms and print any names which correspond with your keyword, together with a corresponding number as in the example below:

Enter keyword of the chemical: CHLORINE

164 CHLORINE  
165 CHLORINE CYANIDE  
166 CHLORINE DIOXIDE  
167 CHLORINE TRIFLUORIDE

SELECT →

You may then choose one of these numbers or return to the INFORMATION SYSTEM MENU by typing (E).

When this Main Selection Display is on the screen, any illegal commands entered by the user will cause a self-explanatory message to appear beside the arrow. These error messages will disappear shortly so you may continue or try to enter another command.

### 3.3.2 Display Routine

The first 20 chemical names of the Synonym Table (see Appendix I) will be displayed.

|    |                             |
|----|-----------------------------|
| 1  | 2 BUTENAL                   |
| 2  | ACETADLDEHYDE               |
| 3  | ACETALDOL                   |
| 4  | ACETIC ACID                 |
| 5  | ACETIC ACID ALLYL ESTER     |
| 6  | ACETIC ACID ISOPROPYL ESTER |
| 7  | ACETIC ACID METHYL ESTER    |
| 8  | ACETIC ANHYDRIDE            |
| 9  | ACETIC ETHER                |
| 10 | ACETIC OXIDE                |
| 11 | ACETIDIN                    |
| 12 | ACETONE                     |
| 13 | ACETONITRILE                |
| 14 | ACETONYL CHLORIDE           |
| 15 | ACETEXUETHANE               |
| 16 | ACETYLENE DICHLORIDE        |
| 17 | ACETYLENE TETRACHLORIDE     |
| 18 | ACRALDEHYDE                 |
| 19 | ACROLEIN                    |
| 20 | ACRYLALDEHYDE               |

\*\*\* TYPE 'H' FOR HELP, \*\*\*

SELECT =====>

You might not see the chemical name that you want. Therefore, you need to "flip" the page back and forth. In order to see the next page, press the (↓) key or (D) (no RETURN) to see the previous page, press the (↑) key or (U) (no RETURN).

If you want to "flip" more than 1 page at a time, keep the (↑) or (↓) key pressed down until you want to stop and see where you are. Remember that the names are listed in alphabetical order. Typing 'H' at this point will produce helpful instructions.

When you have located the chemical name on the screen, type the index number corresponding to that chemical. (This number is on the left side of the name.) Whatever you type in will appear on the screen to the right of "SELECT" in the bottom line.

If the chemical you wish to model is not in the list, go to the Add Routine.

After you type in the index number, press the RETURN key. The information on the requested chemical will be displayed in the following format.

| *** AMMONIA ANHYDROUS ***                                 |  |                   |          |
|---|--|-------------------|----------|
| 1   | FORMULA                                    | NH3               |          |
| 2   | MOLECULAR WEIGHT                           | 17.03             |          |
| 3   | LATENT HEAT                                | 1370              | kJ/kg    |
| 4   | BOILING POINT                              | -33               | deg C    |
| 5   | SOLUBILITY                                 | 89.9              | G/100 ml |
| 6   | SPECIFIC GRAVITY                           | 0.62(LIQ)         |          |
| 7   | VAPOUR PRESSURE                            | 76000(26 C        | mm of Hg |
| 8   | VAPOUR DENSITY                             | 0.6               |          |
| 9   | FLASH POINT                                | NA                |          |
| 10  | IDLH                                       | 355               | mg/m3    |
| 11  | TLV  | 18                | mg/m3    |
| 12  | STEL                                       | 25                | mg/m3    |
| 13  | SP HEAT RATIO(VAP)                         | 1.31              |          |
| 14  | SYNONYMS                                   |                   |          |
|   | 1  | AMMONIA ANHYDROUS |          |
|   | 2  | LIQUID AMMONIA    |          |
| 15  | FIRE HAZARD CODE (PRESS F FOR EXPLANATION) |                   |          |
|   | 3  | 12                |          |
| PRESS 'U'NIT, 'C'HANGE, 'D'ELETE, 'P'RINT, 'E'XIT, 'L'IST |  |                   |          |

All the physical and chemical data are stored and presented in standard units as shown. The information access system will provide information in an alternative set of units (shown below) if requested by the user.

|                    |       |          |
|--------------------|-------|----------|
| AMMONIA ANHYDROUS  | NH3   |          |
| MOLECULAR WEIGHT   | 17.03 |          |
| LATENT HEAT        | 327   | cal/g    |
| BOILING POINT      | -27.4 | deg f    |
| SOLUBILITY         | 89.9  | g/100 ml |
| SPECIFIC GRAVITY   | .62   |          |
| VAPOUR PRESSURE    | 76000 | mm of Hg |
| VAPOUR DENSITY     | .6    |          |
| FLASH POINT        | NA    |          |
| IDLH               | 500   | ppm      |
| TLV                | 25    | ppm      |
| STEL               | 35    | ppm      |
| SP HEAT RATIO(VAP) | 1.31  |          |

In some instances, terms such as "ND", "NF", and "NA" are used. "ND" means that the item could not be found in any of the sources searched. "NF" is used in the Flash Point field and means that the chemical is not flammable and therefore has no flash point. "NA" means that the field is not applicable for the displayed chemical.

The synonyms listed are considered to be the most common, and either the chemical name or the synonyms can be used for accessing the information stored in the system.

At this point, different options are available by pressing the appropriate letters:

- (F) - to display the explanation of fire hazard codes (See Appendix II);
- (U) - to change the display to the alternative set of units (e.g. IDLH, TLV and STEL in ppm);
- (C) - to enter the CHANGE ROUTINE (see below);
- (D) - to delete the chemical record;
- (P) - to print a hard copy on a printer, if available;  
The (Prtsc) button performs the same function;
- (L) - to redisplay the list of chemical names so that another chemical can be selected;
- (E) - to return to the Main Selection Display - any illegal character will have the same effect.

### 3.3.3 Change Routine

The change routine will list physical and chemical properties, each accompanied by an item number and the appropriate unit. The system will also ask the item number of the property whose value you want to change. After typing the number and pressing the (RETURN) key, the system will allow you to enter the new value of that property and ask whether you want to make more changes. A typical dialogue is shown on the next page.

You can change more than one item though you can only change one at a time. When you respond 'N' to the 'More Changes?' question, the new information will be stored on the diskette and re-displayed on the screen.

```

*** AMMONIA ANHYDROUS ***
1  FORMULA
2  MOLECULAR WEIGHT
3  LATENT HEAT           kJ/kg
4  BOILING POINT        deg C
5  SOLUBILITY           g/100 ml
6  SPECIFIC GRAVITY
7  VAPOUR PRESSURE      mm of Hg
8  VAPOUR DENSITY
9  FLASH POINT          deg C
10 IDLH                 ppm
11 TLV                  ppm
12 STEL                 ppm
13 SP HEAT RATIO(VAP)
14 SYNONYMS
15 FIRE HAZARD CODE

CHOOSE NUMBER:?  1
1 FORMULA :  ? NH3
MORE CHANGES?  Y OR N

```

#### 3.3.4 Insert Routine

The system will first ask you to "ENTER NEW CHEMICAL NAME"\*. Then it will ask "ENTER SYNONYM - OR (RETURN) IF FINISHED" so that you can enter all the synonyms. After that, the system will establish a new record in the Information File and prompt you to enter values for the physical and chemical properties. Respond with the corresponding data in the units specified inside brackets in the prompt. When finished, the data will be written in the new record which is, in turn, stored on the diskette. The Main Selection Display will then re-appear. The chemical will be inserted in the list alphabetically.

---

\*All additions and changes should be typed in CAPITAL letters



### 3.3.5 Modify Routine

After displaying a list of the existing properties with the default set of units, the system will ask "WHAT DO YOU WANT TO ADD?". Respond with the property you want to include and the system will ask for its units. The new list of properties will be displayed after the modification has been recorded on the diskette. You can then use the DISPLAY ROUTINE to see that a blank space has been reserved for you to put in the value of the property newly included. Do so by invoking the CHANGE ROUTINE (Section 3.3.3).

### 3.3.6 Delete Routine

When you choose this option, the computer will confirm your choice by asking, "Are you sure (Y/N)?". If you type (Y), it will remove the chemical record from the data files. Note that it will also delete all references under other synonyms so the chemical will no longer be available.

## 3.4 SIMPLE GAS MODEL

### 3.4.1 Selection Phase

The Simple Gas Model Menu below allows you to choose between calculations for the Continuous Release (Plume) Case, the Instantaneous Release (Puff) Case or Source Strength Estimation.

This program is highly user-friendly and step-by-step menus or instructions are displayed on the screen. The following is an example for the concentration calculations in the Continuous Release Case. The first step is to type (1) and press the (RETURN) key from this main menu to choose the Continuous Release Case calculation. Make another choice if you want to run another routine. Then follow displayed instructions which guide you in your calculations.

```
*****
*                                     *
*          SIMPLE GAS MODEL          *
*                                     *
*****

1. Continuous Release Case
2. Instantaneous Release Case
3. Source Emission (Rate) Caln.
4. Quit (Exit to GAS SYSTEM MENU)

SELECT =====>
```

The next menu will allow you to select different routines as shown below:

```
*****
*                                     *
*          CONTINUOUS RELEASE MODEL  *
*                                     *
*****

1. Calculate Concentration.
2. Calculate Emission Rate.
3. Calculate Caution Distance.
4. Quit (Exit to Simple Gas MENU)

SELECT =====>
```

To get into a routine, type the routine number followed by the RETURN key. For example, if you want to calculate the concentration, type (1) and press (RETURN).

You will be asked for some information. Most of these parameters have default values which may be obtained by pressing (RETURN) without typing anything. Examples of certain answers are displayed below.

|                                   |      |          |
|-----------------------------------|------|----------|
| *** CALCULATE CONCENTRATION ***   |      |          |
| EMISSION RATE:                    | 20   | (kg/sec) |
| WINDSPEED:                        | 5    | (m/sec)  |
| DOWN-WIND DISTANCE:               | 5000 | (m)      |
| MIXING LAYER HEIGHT:              | 300  | (m)      |
| VERTICAL FLUCT'N:                 | 0.1  |          |
| HORIZONTAL FLUCT'N:               | 0.17 |          |
| TIME ELAPSED:                     | 3600 | (Sec)    |
| *** PRESS ANY KEY TO CONTINUE *** |      |          |

### 3.4.3 Output Phase

The answer is given in two different units as shown below. To put this concentration into perspective, the IDLH, STEL and TLV values are also quoted in (mg/m<sup>3</sup>).

```

*****
CONCENTRATION
*****

7.34314                                (mg/m3)
4.89688E-07                            (lb./ft3)

*** IDLH:          354.8                (mg/m3) ***
*** STEL:          24.8                  (mg/m3) ***
*** TLV:           17.7                  (mg/m/) ***


*****
PLUME FULL-WIDTH
*****

1700                                (m)
5577.7                             (ft)

* PRESS 'G' FOR GRAPHICS, 'E' TO EXIT *

```

At this point, a graphic display of concentration against distance can be obtained by pressing (G). Note that the concentration scale is logarithmic. The IDLH and TLV levels are also drawn. The IDLH and TLV distances can be easily read from the graph.



Hard copies of this graph can be obtained by pressing the (PrtSc) key if a printer is available.

### 3.5 HEAVY GAS MODEL

\*\*\* Before this can be used, the METINFO MODULE must be run \*\*\*

#### 3.5.1 Input Phase

This model requires the input of 11 parameters. Most of them have default values. These are listed at the beginning of the run. Questions are then presented sequentially as input panels, so that you can supply or change the parameters. A typical input panel is shown below.

[Q6] Amount of the Gas Released

---

ENTER YOUR INPUT HERE      ———>                      (kg)

---

| ENTER | value                  |
|-------|------------------------|
| Qn    | to jump to Question n  |
| L     | to List all parameters |
| <rt>  | to use default value   |
| R     | to Run the model       |
| E     | to Exit                |

The middle area is for receiving input. The upper area displays the default value, if available, and other helpful information. Valid input commands are listed at the bottom. By typing (Q)(n) (RETURN), when n is an integer from 1 to 11 (not the key corresponding to the letter 'n'), you can jump directly to question number 1. Typing (L) (RETURN) will produce a list of the input parameters. Typing (R) (RETURN) or (E) (RETURN) respectively will execute or terminate the model. If you want to use the default value, just press (RETURN). There is no default value for the amount of gas released (Question Q6). The model will not run unless this parameter is supplied.

A typical list of parameters, which will also appear automatically after you answer Question Q11, is as follows:

| LIST OF PARAMETERS                 |                               |       |         |
|------------------------------------|-------------------------------|-------|---------|
| CHEMICAL FORMULA : NH <sub>3</sub> |                               |       |         |
| [Q 1 ]                             | Molecular Weight              | 17.03 |         |
| [Q 2 ]                             | Boiling Point                 | -33   | (deg C) |
| [Q 3 ]                             | Latent Heat, Gas              | 1370  | (kJ/kg) |
| [Q 4 ]                             | Initial Radius                | 45    | (m)     |
| [Q 5 ]                             | Latent Heat, H <sub>2</sub> O | 2260  | (kJ/kg) |
| [Q 6 ]                             | Release Amount                | 1234  | (kg)    |
| [Q 7 ]                             | Gas in Liquid                 | 0.0   |         |
| [Q 8 ]                             | Vert. Entr. Coef.             | 0.4   |         |
| [Q 9 ]                             | Mixing Layer Ht.              | 300   | (m)     |
| [Q 10 ]                            | Water Vapour                  | 0.01  |         |
| [Q 11 ]                            | Display Option                | D     |         |
| * PRESS ANY KEY TO CONTINUE *      |                               |       |         |

You can request a hardcopy by pressing (PrtSc).

### 3.5.2 Execution Phase

You enter the execution phase by pressing (R) when an input panel is displayed. The system will ask "INTERMEDIATE RESULTS NEEDED?". Responding with (Y) (RETURN) will result in a series of displays of the intermediate results such as the mass of air entrained, volume, initial height and density of cloud, and end of slumping phase information. You also have the option to override some of these by answering with (Y) (RETURN) when prompted in each case.

Armed with these intermediate results, the system will go on to calculate the cloud characteristics as a function of downwind distance. You will be asked to enter the range and the increment in distance for which you want the calculation done. Results of this calculation are shown in the following table.

| * CLOUD CHARACTERISTICS * |                   |      |      |                    |               |               |
|---------------------------|-------------------|------|------|--------------------|---------------|---------------|
| Distance Option           |                   |      |      |                    |               |               |
| DIST.<br>(m)              | PASSING-TIME(sec) |      |      | CONC'N.<br>(mg/m3) | RADIUS<br>(m) | HEIGHT<br>(m) |
|                           | Tail              | Cntr | Head |                    |               |               |
| 8                         | 34                | 7    | 0    | 2000000            | 31            | 0.7           |
| 16                        | 43                | 10   | 2    | 2000000            | 36            | 0.5           |
| 24                        | 52                | 12   | 3    | 2000000            | 40            | 0.4           |
| 32                        | 63                | 15   | 5    | 2000000            | 44            | 0.3           |
| 40                        | 65                | 18   | 7    | 2000000            | 49            | 0.3           |
| 48                        | 67                | 21   | 9    | 2000000            | 53            | 0.2           |
| 56                        | 69                | 24   | 10   | 2000000            | 56            | 0.2           |
| 64                        | 70                | 28   | 12   | 2000000            | 60            | 0.2           |
| 72                        | 72                | 32   | 14   | 2000000            | 64            | 0.2           |
| 80                        | 74                | 36   | 16   | 2000000            | 68            | 0.1           |
| 88                        | 76                | 40   | 18   | 2000000            | 72            | 0.1           |
| 96                        | 78                | 44   | 20   | 2000000            | 76            | 0.1           |
| 104                       | 79                | 49   | 22   | 2000000            | 80            | 0.1           |
| 112                       | 81                | 53   | 24   | 2000000            | 83            | 0.1           |
| → Phase two               |                   |      |      |                    |               |               |
| 120                       | 83                | 56   | 26   | 743307             | 86            | 0.2           |
| 128                       | 84                | 59   | 29   | 282769             | 87            | 0.6           |
| 136                       | 86                | 61   | 31   | 176549             | 89            | 0.9           |
| 144                       | 88                | 63   | 34   | 128473             | 91            | 1.2           |
| 152                       | 89                | 65   | 37   | 100800             | 92            | 1.5           |
| 160                       | 91                | 67   | 40   | 82720              | 93            | 1.8           |

This table of cloud characteristics gives, for each downwind distance, the time after release at which the centre, the head and the tail of the cloud passes through that point. If you prefer, the location of the centre, head and tail of cloud can be obtained as a function of time by selecting the time option in question 11.



Results are then displayed as in the following table. The difference of the latter two times gives the time of exposure. The display also gives the toxic gas concentration at the cloud centre, the radius and height of the cloud when the cloud is centred at that particular distance. For comparison, the IDLH, STEL and TLV values are displayed on the screen.

| * CLOUD CHARACTERISTICS * |                   |      |      |                    |               |               |
|---------------------------|-------------------|------|------|--------------------|---------------|---------------|
| Time Option               |                   |      |      |                    |               |               |
| TIME<br>(sec)             | CLOUD-LOCATION(m) |      |      | CONC'N.<br>(mg/m3) | RADIUS<br>(m) | HEIGHT<br>(m) |
|                           | Tail              | Cntr | Head |                    |               |               |
| 0                         | -7                | 0    | 7    | 2000000            | 7             | 13.8          |
| 5                         | -22               | 4    | 30   | 2000000            | 26            | 0.9           |
| 10                        | -21               | 16   | 53   | 2000000            | 37            | 0.5           |
| 15                        | -14               | 31   | 75   | 2000000            | 45            | 0.3           |
| 20                        | -7                | 44   | 95   | 2000000            | 51            | 0.2           |
| 25                        | -1                | 56   | 113  | 2000000            | 57            | 0.2           |
| 30                        | 4                 | 67   | 130  | 2000000            | 63            | 0.2           |
| 35                        | 10                | 77   | 145  | 2000000            | 68            | 0.1           |
| 40                        | 15                | 87   | 159  | 2000000            | 72            | 0.1           |
| 50                        | 24                | 104  | 185  | 2000000            | 81            | 0.1           |
| 55                        | 28                | 112  | 197  | 2000000            | 85            | 0.1           |
| —> Phase two              |                   |      |      |                    |               |               |
| 60                        | 38                | 127  | 215  | 212270             | 88            | 0.8           |
| 65                        | 55                | 147  | 239  | 98105              | 92            | 1.5           |
| 70                        | 74                | 170  | 266  | 60437              | 96            | 2.3           |
| 75                        | 96                | 195  | 295  | 41979              | 100           | 3.0           |
| 80                        | 118               | 222  | 325  | 31181              | 104           | 3.8           |
| 85                        | 142               | 249  | 356  | 24186              | 107           | 4.6           |
| 90                        | 166               | 277  | 389  | 19343              | 111           | 5.3           |
| 95                        | 192               | 307  | 421  | 15827              | 115           | 6.1           |
| 100                       | 218               | 336  | 455  | 13185              | 119           | 6.8           |

Figure 5 is a graph of concentration against downwind distance predicted by both the Heavy Gas Model and the Simple Gas Model for an instantaneous release of 20,000 kg of ammonia. The agreement between the two models is fairly good. During the slumping phase, the concentration predicted by the Heavy Gas Model remains at a constant high value. This is more realistic than the Simple Gas Model, which predicts infinite concentration at zero distance. A plot of the height of the cloud versus time is shown in Figure 6. The height decreases rapidly at the beginning. It drops to a minimum at the end of the slumping phase and then increases again when atmospheric turbulence dominates. This figure agrees reasonably well with Figure 3 in Kaiser and Walker's (1978) paper, which gives a plot of the height as a function of time, using a more "complete" model.




FIGURE 5




FIGURE 6

### 3.5.3 Summary of Valid Entries for the Heavy Gas Model

During the input phase you may enter

a number

- any number in the form acceptable by BASIC syntax.

e.g. 1.1234

-123.09

.023

3.5D2

7E-3

-.234E-21

(Q)(n)

- where n is an integer between 1 and 14, to bring you Question n.

(L)

- to list all the parameters with input or default values. Then you can press (P) to get a hardcopy. Note that some physical properties are taken directly from the information access program. The chemical last accessed when you run the INFORMATION ACCESS program is used as default.

(T) or (D)

- Question 11 only. Selects time or distance option.

(R)

- to execute the model.

(E)

- to terminate the model and return to GAS SYSTEM MENU.

### 3.6 METINFO

The METINFO routine asks the user a series of 9 questions to supply the computer with information needed for the calculations in the heavy gas model.

\*\*\* METEOROLOGICAL INFORMATION \*\*\*

- |  |   |            |
|--|---|------------|
| 1. Enter time                              | = | (hh mm)    |
| 2. Enter date                              | = | (mm dd yy) |
| 3. Wind speed at 10 metres                 | = | (m/s)      |
| 4. Temperature at 10 metres                | = | (degree C) |
| 5. Atmosphere pressure                     | = | (KPa)      |
| 6. Cloud cover (0 : clear to 8 : overcast) | = |            |
| 7. Longitude of spill location             | = | (degree)   |
| 8. Latitude of spill location              | = | (degree)   |
| 9. Surface roughness                       | = | (m)        |
| Default value of No. 1                     | = | No         |

Questions 3 - 9 have default values which can be obtained by hitting (RETURN). They may, however, be inappropriate for your location or situation. The default values are previewed in the shaded box on the bottom line.

When you have entered all the values, you will be given a chance to change any you may have mistyped.

The computer will then store the data in a file for the Heavy Gas System to use.

## **CHAPTER 4: PROGRAMS**

#### 4.1 SYSTEM DESIGN AND FLOW CHARTS

This version of the Portable Computing System for Use in Toxic Gas Emergencies (the GAS SYSTEM) was developed for use in an IBM/PC micro-computer, with two-sided floppy disk drives. If a hard disk is available, the programs and files may be transferred to it. It requires 640K of random access memory. The programs are interactively written in Basic using the MS-DOS (or equivalent) operating system. Programs and files are stored on two 5 $\frac{1}{4}$  inch double-density diskettes along with an advanced Basic interpreter and some utility program modules.


The GAS SYSTEM is menu-driven and consists of the following three main programs:

- 1) SIMPLE - the Simple Gas Model
- 2) HEAVY3 - the Heavy Gas Model
- 3) INFO2 - the Information Sub-System


Flow charts on the following pages outline the functions of various programs and routines, as well as their inter-relationship. More detailed description is given in the User's Manual (Chapter 3).




# GAS SYSTEM




## SIMPLE GAS MODEL




# HEAVY GAS MODEL




# INFORMATION SYSTEM



# DISPLAY ROUTINE



**DISPLAY ROUTINE (CONT.)**

## 4.2 FILE STRUCTURES FOR INFORMATION SUB-SYSTEM

### 4.2.1 Information File

This is actually made up by joining two random access files, INFO1.RAF and INFO2.RAF. The resulting file structure has an effective record length of 237 characters distributed among 26 fields as follows:

| <u>FIELD</u> | <u>FIELD NAME</u>    | <u>LENGTH</u> |
|--------------|----------------------|---------------|
| 1            | Chemical Formula     | 16            |
| 2            | Molecular Weight     |               |
| 3            | Latent Heat          | 10            |
| 4            | Boiling Point        |               |
| 5            | Solubility           | 16            |
| 6            | Specific Gravity     |               |
| 7            | Vapour Pressure      |               |
| 8            | Vapour Density       |               |
| 9            | Flash Point          | 10            |
| 10           | IDLH                 |               |
| 11           | TLV                  |               |
| 12           | STEL                 |               |
| 13           | Specific Heat Ratio  |               |
| 14-21        | for future expansion | 10 each       |
| 22-26        | Fire Hazard Code     | 3 each        |

The chemicals are arranged in alphabetical order, and assigned consecutive record numbers. These are used by the program to retrieve the record containing the information on the respective chemicals.

#### 4.2.2 Chemical Name File

Most of the chemicals have more than one name (synonyms). These various chemical names are stored in a sequential file CHEM.NAM. Each name is paired with the record number used to retrieve the appropriate record from the Information File. The program will load the content of this file into two tables with a common index:

Synonym Table (array STN\$) - containing the synonyms.

Synonym Table Link (array STL) - containing the record numbers.

#### 4.2.3 Synonym File

This sequential file, named SYNO.NAM, contains groups of numerical indices delimited by zeros. Each group contains all the indices to retrieve the synonyms of a particular chemical from the Synonym Table (array STN\$).

#### 4.2.4 Parameters File

The contents of this sequential file PARA.NAM are labels of the physical and chemical properties (i.e. field names of the Information File) and their associated units.



## **APPENDIX**

I. SYNONYM TABLE

| <u>INDEX</u> | <u>SYNONYM</u>              | <u>CHEMICAL NAME</u> |
|--------------|-----------------------------|----------------------|
| 1.           | 2 BUTENAL                   | CROTON ALDEHYDE      |
| 2.           | ACETALDEHYDE                | ACETALDEHYDE         |
| 3.           | ACETALDOL                   | ALDOL                |
| 4.           | ACETIC ACID                 | ACETIC ACID          |
| 5.           | ACETIC ACID ALLYL ESTER     | ALLYL ACETATE        |
| 6.           | ACETIC ACID ISOPROPYL ESTER | ISOPROPYL ACETATE    |
| 7.           | ACETIC ACID METHYL ESTER    | METHYL ACETATE       |
| 8.           | ACETIC ANHYDRIDE            | ACETIC ANHYDRIDE     |
| 9.           | ACETIC ETHER                | ETHYL ACETATE        |
| 10.          | ACETIC OXIDE                | ACETIC ANHYDRIDE     |
| 11.          | ACETIDIN                    | ETHYL ACETATE        |
| 12.          | ACETONE                     | ACETONE              |
| 13.          | ACETONITRILE                | ACETONITRILE         |
| 14.          | ACETONYL CHLORIDE           | CHLOROACETONE        |
| 15.          | ACETOXYETHANE               | ETHYL ACETATE        |
| 16.          | ACETYLENE DICHLORIDE        | DICHLOROETHYLENE     |
| 17.          | ACETYLENE TETRACHLORIDE     | TETRACHLOROETHANE    |
| 18.          | ACRALDEHYDE                 | ACROLEIN             |
| 19.          | ACROLEIN                    | ACROLEIN             |
| 20.          | ACRYLALDEHYDE               | ACROLEIN             |
| 21.          | ACRYLAMIDE                  | ACRYLAMIDE           |
| 22.          | ACRYLIC ACID BUTYL ESTER    | N-BUTYL ACRYLATE     |
| 23.          | ACRYLIC ACID ETHYL ESTER    | ETHYL ACRYLATE       |
| 24.          | ACRYLIC ALDEHYDE            | ACROLEIN             |
| 25.          | ACRYLIC AMIDE 50%           | ACRYLAMIDE           |
| 26.          | ACRYLONITRILE               | ACRYLONITRILE        |
| 27.          | ALBONE                      | HYDROGEN PEROXIDE    |
| 28.          | ALDOL                       | ALDOL                |
| 29.          | ALLTEX                      | TOXAPHENE            |
| 30.          | ALLYL ACETATE               | ALLYL ACETATE        |
| 31.          | ALLYL ALCOHOL               | ALLYL ALCOHOL        |

| <u>INDEX</u> | <u>SYNONYM</u>               | <u>CHEMICAL NAME</u>   |
|--------------|------------------------------|------------------------|
| 32.          | ALLYL BROMIDE                | ALLYL BROMIDE          |
| 33.          | ALLYL CHLORIDE               | ALLYL CHLORIDE         |
| 34.          | ALLYL FORMATE                | ALLYL FORMATE          |
| 35.          | ALLYLAMINE                   | ALLYLAMINE             |
| 36.          | ALLYLIC ALCOHOL              | ALLYL ALCOHOL          |
| 37.          | ALPHA-DICHLOROPROPIONIC ACID | DICHLOROPROPIONIC ACID |
| 38.          | ALUMINUM CHLORIDE            | ALUMINUM CHLORIDE      |
| 39.          | AMINOANISOLE                 | ANSIDINE               |
| 40.          | AMINO BENZENE                | ANILINE                |
| 41.          | AMINO BUTANE                 | BUTYLAMINE             |
| 42.          | AMINOCAPROIC LACTAM          | CAPROLACTAM            |
| 43.          | AMINOCYCLOHEXANE             | CYCLOHEXYLAMINE        |
| 44.          | AMINOETHANE                  | ETHYLAMINE             |
| 45.          | 2-AMINOETHANOL               | MONOETHANOLAMINE       |
| 46.          | beta-AMINOETHYL ALCOHOL      | MONOETHANOLAMINE       |
| 47.          | AMINOETHYLENE                | ETHYLENEIMINE          |
| 48.          | AMINOMETHANE                 | METHYLAMINE            |
| 49.          | AMINOPROPENE                 | ALLYLAMINE             |
| 50.          | AMINOPYRIDINE                | AMINOPYRIDINE          |
| 51.          | AMINOTOLUENE                 | TOLUIDINE              |
| 52.          | AMMONIA ANHYDROUS            | AMMONIA ANHYDROUS      |
| 53.          | AMMONIA WATER                | AMMONIA HYDROXIDE      |
| 54.          | AMMONIUM CHLORIDE            | AMMONIUM CHLORIDE      |
| 55.          | AMMONIUM HYDROXIDE           | AMMONIUM HYDROXIDE     |
| 56.          | AMMONIUM MURIATE             | AMMONIUM CHLORIDE      |
| 57.          | n-AMYL ALCOHOL               | n-AMYL ALCOHOL         |
| 58.          | 1-AMYL ALCOHOL               | n-AMYL ALOCHOL         |
| 59.          | AMYL ALDEHYDE                | VALERALDEHYDE          |
| 60.          | AMYL HYDRIDE                 | PENTANE                |
| 61.          | ANHYDROUS ALUMINUM CHLORIDE  | ALUMINUM CHLORIDE      |
| 62.          | ANILINE                      | ANILINE                |
| 63.          | ANILINE OIL                  | ANILINE                |
| 64.          | ANILINOBENZENE               | DIPHENYLAMINE          |
| 65.          | ANISIDINE                    | ANSIDINE               |
| 66.          | ANSIDINE                     | ANSIDINE               |
| 67.          | ANTIMONIC CHLORIDE           | ANTIMONY PENTACHLORIDE |

| <u>INDEX</u> | <u>SYNONYM</u>         | <u>CHEMICAL NAME</u>     |
|--------------|------------------------|--------------------------|
| 68.          | ANTIMONY PENTACHLORIDE | ANTIMONY PENTACHLORIDE   |
| 69.          | ANTIMONY PENTAFLUORIDE | ANTIMONY PENTAFLUORIDE   |
| 70.          | ANTIMONY PERCHLORIDE   | ANTIMONY PENTACHLORIDE   |
| 71.          | ANTIMONY TRIHYDRIDE    | STIBINE                  |
| 72.          | ANTIMONY V             | ANTIMONY PENTAFLUORIDE   |
| 73.          | AQUA FORTIS            | NITRIC ACID              |
| 74.          | AQUALIN                | ACROLEIN                 |
| 75.          | AQUALINE               | ACROLEIN                 |
| 76.          | AQUEOUS AMMONIA        | AMMONIUM HYDROXIDE       |
| 77.          | AROCLOR                | POLYCHLORINATED BIPHENYL |
| 78.          | ARSENIC ACID           | ARSENIC ACID             |
| 79.          | ARSENIC ANHYDRIDE      | ARSENIC ACID             |
| 80.          | ARSENIC DICHLOROETHANE | ETHYLDICHLOROARSINE      |
| 81.          | ARSENIC PENTAOXIDE     | ARSENIC ACID             |
| 82.          | ARSENIC PENTOXIDE      | ARSENIC ACID             |
| 83.          | ASKAREL                | POLYCHLORINATED BIPHENYL |
| 84.          | ASYM DIMETHYLHYDRAZINE | DIMETHYLHYDRAZINE        |
| 85.          | AZCYCLOPROPANE         | ETHYLENEIMINE            |
| 86.          | AZIRANE                | ETHYLENEIMINE            |
| 87.          | AZIRIDINE              | ETHYLENEIMINE            |
| 88.          | AZOTIC ACID            | NITRIC ACID              |
| 89.          | BATTERY ACID           | SULPHURIC ACID           |
| 90.          | BENZENE                | BENZENE                  |
| 91.          | BENZENETHIOL           | PHENYL MERCAPTAN         |
| 92.          | BENZOL                 | BENZENE                  |
| 93.          | BENZOLE                | BENZENE                  |
| 94.          | BENZYL CHLORIDE        | BENZYL CHLORIDE          |
| 95.          | BETA-CHLOROPRENE       | CHLOROPRENE              |
| 96.          | BICYCLOPENTADIENE      | DICYCLOPENTADIENE        |
| 97.          | BIETHYLENE             | BUTADIENE                |
| 98.          | BISCYCLOPENTADIENE     | DICYCLOPENTADIENE        |
| 99.          | BIVINYL                | BUTADIENE                |
| 100.         | BLUE OIL               | ANILINE                  |
| 101.         | BORNANONE              | CAMPHOR                  |
| 102.         | BOROETHANE             | DIBORANE                 |
| 103.         | BORON CHLORIDE         | BORON TRICHLORIDE        |

| <u>INDEX</u> | <u>SYNONYM</u>            | <u>CHEMICAL NAME</u>      |
|--------------|---------------------------|---------------------------|
| 104.         | BORON FLUORIDE            | BORON TRIFLUORIDE         |
| 105.         | BORON HYDRIDE             | DIBORANE                  |
| 106.         | BORON TRICHLORIDE         | BORON TRICHLORIDE         |
| 107.         | BORON TRIFLUORIDE         | BORON TRIFLUORIDE         |
| 108.         | BROMALLYLENE              | ALLYL BROMIDE             |
| 109.         | BROMINE                   | BROMINE                   |
| 110.         | BROMINE PENTAFLUORIDE     | BROMINE PENTAFLUORIDE     |
| 111.         | BROMOETHANE               | ETHYL BROMIDE             |
| 112.         | BROMOETHENE               | VINYL ETHENE              |
| 113.         | BROMOETHYLENE             | VINYL ETHYLENE            |
| 114.         | BROMOFORM                 | BROMOFORM                 |
| 115.         | BROMOFORME                | BROMOFORM                 |
| 116.         | BROMOETHANE               | METHYL BROMIDE            |
| 117.         | BUTADIENE                 | BUTADIENE                 |
| 118.         | BUTAMINE                  | BUTYLAMINE                |
| 119.         | BUTANE                    | BUTANE                    |
| 120.         | BUTANE NITRILE            | BUTYRONITRILE             |
| 121.         | BUTANETHIOL               | BUTYL MERCAPTAN           |
| 122.         | BUTANOIC ACID ETHYL ESTER | ETHYL BUTYRATE            |
| 123.         | BUTEN-3-ONE               | METHYL VINYL KETONE       |
| 124.         | BUTYL ACRYLATE            | n-BUTYL ACRYLATE          |
| 125.         | n-BUTYL ACRYLATE          | n-BUTYL ACRYLATE          |
| 126.         | BUTYL ALDEHYDE            | BUTYRALDEHYDE             |
| 127.         | n-BUTYLCARBINOL           | n-AMYL ALCOHOL            |
| 128.         | n-BUTYL 2-PROPENOATE      | n-BUTYL ACRYLATE          |
| 129.         | BUTYL FORMAL              | VALERALDEHYDE             |
| 130.         | BUTYL HYDRIDE             | BUTANE                    |
| 131.         | BUTYL MERCAPTAN           | BUTYL MERCAPTAN           |
| 132.         | BUTYL VINYL ETHER         | BUTYL VINYL ETHER         |
| 133.         | BUTYLAMINE                | BUTYLAMINE                |
| 134.         | BUTYRAL                   | BUTYRALDEHYDE             |
| 135.         | BUTYRALDEHYDE             | BUTYRALDEHYDE             |
| 136.         | BUTYRIC ACID EHTYL ESTER  | ETHYL BUTYRATE            |
| 137.         | BUTYRIC ALDEHYDE          | BUTYRALDEHYDE             |
| 138.         | BUTYRONITRILE             | BUTYRONITRILE             |
| 139.         | C 56                      | HEXACHLOROCYCLOPENTADIENE |

| <u>INDEX</u> | <u>SYNONYM</u>            | <u>CHEMICAL NAME</u>     |
|--------------|---------------------------|--------------------------|
| 140.         | CALCIUM OXIDE             | CALCIUM OXIDE            |
| 141.         | CALX                      | CALCIUM OXIDE            |
| 142.         | CAMPHANONE                | CAMPHOR                  |
| 143.         | CAMPHECHLOR               | TOXAPHENE                |
| 144.         | CAMPHOR                   | CAMPHOR                  |
| 145.         | CAPROLACTAM               | CAPROLACTAM              |
| 146.         | CARBANIL                  | PHENYL ISOCYANATE        |
| 147.         | CARBOLIC ACID             | PHENOL                   |
| 148.         | CARBON BISULPHIDE         | CARBON DISULPHIDE        |
| 149.         | CARBON CHLOROSULPHIDE     | THIOPHOSGENE             |
| 150.         | CARBON DISULPHIDE         | CARBON DISULPHIDE        |
| 151.         | CARBON MONOXIDE           | CARBON MONOXIDE          |
| 152.         | CARBON OXIDE              | CARBON MONOXIDE          |
| 153.         | CARBON OXIDE SULPHIDE     | CARBONYL SULPHIDE        |
| 154.         | CARBON OXYCHLORIDE        | PHOSGENE                 |
| 155.         | CARBON OXYSULPHIDE        | CARBONYL SULPHIDE        |
| 156.         | CARBON TET                | CARBON TETRACHLORIDE     |
| 157.         | CARBON TETRABROMIDE       | TETRABROMOETHANE         |
| 158.         | CARBON TETRACHLORIDE      | CARBON TETRACHLORIDE     |
| 159.         | CARBONIC DICHLORIDE       | PHOSGENE                 |
| 160.         | CARBONYL CHLORIDE         | PHOSGENE                 |
| 161.         | CARBONYL SULPHIDE         | CARBONYL SULPHIDE        |
| 162.         | CHLORALLYLENE             | ALLYL CHLORIDE           |
| 163.         | CHLORINATED BIPHENYL      | POLYCHLORINATED BIPHENYL |
| 164.         | CHLORINE                  | CHLORINE                 |
| 165.         | CHLORINE CYANIDE          | CYANOGEN CHLORIDE        |
| 166.         | CHLORINE DIOXIDE          | CHLORINE DIOXIDE         |
| 167.         | CHLORINE TRIFLUORIDE      | CHLORINE TRIFLUORIDE     |
| 168.         | 1-CHLORO-2,3-EPOXYPROPANE | EPICHLOROHYDRIN          |
| 169.         | CHLORO-2-KETOPROPANE      | CHLOROACETONE            |
| 170.         | CHLORO-2-OXOPROPANE       | CHLOROACETONE            |
| 171.         | CHLOROACETALDEHYDE        | CHLOROACETALDEHYDE       |
| 172.         | CHLOROACETONE             | CHLOROACETONE            |
| 173.         | CHLOROACETONITRILE        | CHLOROACETONITRILE       |

| <u>INDEX</u> | <u>SYNONYM</u>                    | <u>CHEMICAL NAME</u>     |
|--------------|-----------------------------------|--------------------------|
| 174.         | CHLOROBUTADIENE                   | CHLOROPRENE              |
| 175.         | CHLOROCAMPHENE                    | TOXAPHENE                |
| 176.         | CHLOROCYAN                        | CYANOGEN CHLORIDE        |
| 177.         | CHLOROCYANIDE                     | CYANOGEN CHLORIDE        |
| 178.         | CHLOROCYANOGEN                    | CYANOGEN CHLORIDE        |
| 179.         | CHLORODIFLUOROMETHANE             | CHLORODIFLUOROMETHANE    |
| 180.         | CHLOROETHANAL                     | CHLOROACETALDEHYDE       |
| 181.         | CHLOROETHANE                      | ETHYL CHLORIDE           |
| 182.         | CHLOROETHANOL                     | ETHYLENE CHLOROHYDRIN    |
| 183.         | CHLOROETHENE                      | VINYL CHLORIDE           |
| 184.         | CHLOROETHYLENE                    | VINYL CHLORIDE           |
| 185.         | CHLOROFORM                        | CHLOROFORM               |
| 186.         | CHLOROFORMIC ACID ISOPROPYL ESTER | ISOPROPYL CHLOROFORMATE  |
| 187.         | CHLOROFORMYL CHLORIDE             | PHOSGENE                 |
| 188.         | CHLOROMETHANE                     | METHYL CHLORIDE          |
| 189.         | CHLOROMETHYL CYANIDE              | CHLOROACETONITRILE       |
| 190.         | CHLOROMETHYLBENZENE               | BENZYL CHLORIDE          |
| 191.         | CHLOROPENTAFLUOROETHANE           | CHLOROPENTAFLUOROETHANE  |
| 192.         | CHLOROPHENYLMETHANE               | BENZYL CHLORIDE          |
| 193.         | CHLOROPICRIN                      | CHLOROPICRINE            |
| 194.         | CHLOROPICRINE                     | CHLOROPICRINE            |
| 195.         | CHLOROPRENE                       | CHLOROPRENE              |
| 196.         | gamma-CHLOROPROPYLENE OXIDE       | EPICHLOROHYDRIN          |
| 197.         | CHLOROPYRIDINE                    | CHLOROPYRIDINE           |
| 198.         | CHLOROSULPHONIC ACID              | CHLOROSULPHONIC ACID     |
| 199.         | CHLOROTOLUENE                     | BENZYL CHLORIDE          |
| 200.         | CHLOROTRIMETHYLSILANE             | TRIMETHYLCHLOROSILANE    |
| 201.         | CHLORSULPHONIC ACID               | CHLOROSULPHONIC ACID     |
| 202.         | CHLORURE DE CYANOGENE             | CYANOGEN CHLORIDE        |
| 203.         | CLAIRSIT                          | PERCHLOROMETHYLMERCAPTAN |
| 204.         | CMDP                              | MEVINPHOS                |
| 205.         | COAL GAS                          | CARBON MONOXIDE          |
| 206.         | CRESOLS                           | CRESOLS                  |
| 207.         | CRESYLIC ACID                     | CRESOLS                  |
| 208.         | CROTONAL                          | CROTONALDEHYDE           |
| 209.         | CROTONALDEHYDE                    | CROTONALDEHYDE           |

| <u>INDEX</u> | <u>SYNONYM</u>          | <u>CHEMICAL NAME</u>           |
|--------------|-------------------------|--------------------------------|
| 210.         | CROTONIC ALDEHYDE       | CROTONALDEHYDE                 |
| 211.         | CUMENE                  | ISOPROPYL BENZENE              |
| 212.         | CYANOETHANE             | PROPIONITRILE                  |
| 213.         | CYANOGEN                | CYANOGEN                       |
| 214.         | CYANOGEN CHLORIDE       | CYANOGEN CHLORIDE              |
| 215.         | CYANOGRAN               | SODIUM CYANIDE                 |
| 216.         | CYANOETHYLENE           | ACRYLONITRILE                  |
| 217.         | CYANOMETHANE            | ACETONITRILE                   |
| 218.         | CYCLOHEPTATRIENE        | CYCLOHEPTATRIENE               |
| 219.         | CYCLOHEXANE             | CYCLOHEXANE                    |
| 220.         | CYCLOHEXYAMINE          | CYCLOHEXYAMINE                 |
| 221.         | CYCLOPENTANE            | CYCLOPENTANE                   |
| 222.         | 2,4-D                   | 2,4-DICHLOROPHENOXYACETIC ACID |
| 223.         | DALAPON                 | DICHLOROPROPIONIC ACID         |
| 224.         | DCPD                    | DICYCLOPENTADIENE              |
| 225.         | DI-N-AMYLAMINE          | DI-N-AMYLAMINE                 |
| 226.         | DIAMINE                 | HYDRAZINE                      |
| 227.         | DIAMINOETHANE           | ETHYLENEDIAMINE                |
| 228.         | 1,6-DIAMINOHEXANE       | HEXAMETHYLENEDIAMINE           |
| 229.         | DIAMYL AMINE            | DI-N-AMYLAMINE                 |
| 230.         | DIBORANE                | DIBORANE                       |
| 231.         | DIBORON HEXAHYDRIDE     | DIBORANE                       |
| 232.         | 1,2-DIBROMOETHANE       | ETHYLENE DIBROMIDE             |
| 233.         | DICHLORIDE              | 1,4-DICHLOROBENZENE            |
| 234.         | 1,4-DICHLOROBENZENE     | 1,4-DICHLOROBENZENE            |
| 235.         | p-DICHLOROBENZENE       | 1,4-DICHLOROBENZENE            |
| 236.         | DICHLOROBUTENE          | DICHLOROBUTENE                 |
| 237.         | DICHLORODIFLUOROMETHANE | DICHLORODIFLUOROMETHANE        |
| 238.         | DICHLORODIMETHYLSILANE  | DIMETHYLDICHLOROSILANE         |
| 239.         | 1,2-DICHLOROETHANE      | ETHYLENE DICHLORIDE            |
| 240.         | DICHLOROETHANE          | DICHLOROETHANE                 |
| 241.         | DICHLOROETHYLARSINE     | ETHYLDICHLOROARSINE            |
| 242.         | DICHLOROETHYLENE        | DICHLOROETHYLENE               |
| 243.         | DICHLOROFLUOROMETHANE   | DICHLOROFLUOROMETHANE          |
| 244.         | DICHLROMETHANE          | DICHLROMETHANE                 |
| 245.         | DICHLROMETHYLARSINE     | METHYLDICHLOROARSINE           |



| <u>INDEX</u> | <u>SYNONYM</u>                 | <u>CHEMICAL NAME</u>       |
|--------------|--------------------------------|----------------------------|
| 246.         | DICHLORONITROETHANE            | DICHLORONITROETHANE        |
| 247.         | 2,4-DICHLOROPHENOXYACETIC ACID | DICHLOROPHENOXYACETIC ACID |
| 248.         | DICHLOROPROPANE                | PROPYLENE DICHLORIDE       |
| 249.         | DICHLOROPROPENE                | DICHLOROPROPENE            |
| 250.         | DICHLOROPROPIONIC ACID         | DICHLOROPROPIONIC ACID     |
| 251.         | DICHLOROTETRAFLUOROETHANE      | DICHLOROTETRAFLUOROETHANE  |
| 252.         | DICYANOGEN                     | CYANOGEN                   |
| 253.         | DICYCLOPENTADIENE              | DICYCLOPENTADIENE          |
| 254.         | DIETHYL ETHER                  | DIETHYL ETHER              |
| 255.         | DIETHYL KETONE                 | DIETHYL DETONE             |
| 256.         | DIETHYL OXIDE                  | DIETHYL ETHER              |
| 257.         | DIETHYL SULPHIDE               | DIETHYL SULPHIDE           |
| 258.         | DIETHYLAMINE                   | DIETHYLAMINE               |
| 259.         | DIETHYLENE ETHER               | DIOXANE                    |
| 260.         | DIETHYLENEIMIDE OXIDE          | MORPHOLINE                 |
| 261.         | DIETHYLETHANAMINE              | DIETHYLAMINE               |
| 262.         | DIETHYLTHIOETHER               | DIETHYL SULPHIDE           |
| 263.         | DIFLUOROCHLOROMETHANE          | CHLORODIFLUOROMETHANE      |
| 264.         | DIFLUOROMONOCHLOROMETHANE      | CHLORODIFLUOROMETHANE      |
| 265.         | DIHYDROGEN SELENIDE            | HYDROGEN SELENIDE          |
| 266.         | DIISOBUTYLAMINE                | DIISOBUTYLAMINE            |
| 267.         | DIISOBUTYLENE                  | DIISOBUTYLENE              |
| 268.         | DIISOPROPYL ETHER              | DIISOPROPYL ETHER          |
| 269.         | DIISOPROPYL OXIDE              | DIISOPROPYL ETHER          |
| 270.         | DIISOPROPYLAMINE               | DIISOPROPYLAMINE           |
| 271.         | DIMETHOXYMETHANE               | METHYLAL                   |
| 272.         | DIMETHYL ACETIC ACID           | ISOBUTRIC ACID             |
| 273.         | DIMETHYL ETHER                 | DIMETHYL ETHER             |
| 274.         | DIMETHYL FORMALDEHYDE          | ACETONE                    |
| 275.         | DIMETHYL KETONE                | ACETONE                    |
| 276.         | DIMETHYL MONOSULPHATE          | DIMETHYL SULPHATE          |
| 277.         | DIMETHYL PARATHION             | METHYL PARATHION           |
| 278.         | DIMETHYL SULPHATE              | DIMETHYL SULPHATE          |
| 279.         | DIMETHYL SULPHIDE              | DIMETHYL SULPHIDE          |
| 280.         | DIMETHYLACETONE                | DIETHYL KETONE             |
| 281.         | DIMETHYLAMINE                  | DIMETHYLAMINE              |

| <u>INDEX</u> | <u>SYNONYM</u>                       | <u>CHEMICAL NAME</u>        |
|--------------|--------------------------------------|-----------------------------|
| 282          | DIMETHYLAMINO BENZENE                | DIMETHYLANILINE             |
| 283          | DIMETHYLANILINE                      | DIMETHYLANILINE             |
| 284          | DIMETHYLBENZENES                     | XYLENES                     |
| 285          | DIMETHYLDICHLOROSILANE               | DIMETHYLDICHLOROSILANE      |
| 286          | DIMETHYLENEIMINE                     | ETHYLENEIMINE               |
| 287          | DIMETHYLFORMAL                       | METHYLAL                    |
| 288          | DIMETHYLHYDRAZINE                    | DIMETHYLHYDRAZINE           |
| 289          | DIMETHYLPHENYLAMINE                  | DIMETHYLANILINE             |
| 290          | DINITROBENZENE                       | DINITROBENZENE              |
| 291          | DINITROTOLUENE                       | DINITROTOLUENE              |
| 292          | DINITROTOLUOL                        | DINITROTOLUENE              |
| 293          | DIOXAN                               | DIOXANE                     |
| 294          | DIOXANE                              | DIOXANE                     |
| 295          | DIOXANNE                             | DIOXANNE                    |
| 296          | DIPHENYLAMINE                        | DIPHENYLAMINE               |
| 297.         | DIPHENYLMETHANEDIISOCYANATE          | DIPHENYLMETHANEDIISOCYANATE |
| 298.         | DIPHENYLMETHANE-4,<br>4-DIISOCYANATE | DIPHENYLMETHANEDIISOCYANATE |
| 299.         | DIPROPYLMETHANE                      | HEPTANE                     |
| 300.         | DIVINYL ETHER                        | DIVINYL ETHER               |
| 301.         | DMH                                  | DIMETHYLHYDRAZINE           |
| 302.         | DMS                                  | DIETHYL SULPHATE            |
| 303.         | DOWICIDE                             | PENTACHLOROPHENOL           |
| 304.         | EB                                   | ETHYLBENZENE                |
| 305.         | EDB                                  | ETHYLENE DIBROMIDE          |
| 306.         | EDC                                  | ETHYLENE DICHLORIDE         |
| 307.         | EI                                   | ETHYLENEIMINE               |
| 308.         | ELEMENTAL PHOSPHORUS                 | PHOSPHORUS                  |
| 309.         | ENT-50324                            | ETHYLENEIMINE               |
| 310.         | EPICHLOROHYDRIN                      | EPICHLOROHYDRIN             |
| 311.         | 1,2-EPOXYETHANE                      | ETHYLENE OXIDE              |
| 312.         | 1,2-EPOXYPROPANE                     | PROPYLENE OXIDE             |
| 313.         | ERYTHENE                             | BUTADIENE                   |
| 314.         | ETHANAL ACETIC ALDEHYDE              | ACETALDEHYDE                |
| 315.         | ETHANE PENTACHLORIDE                 | PENTACHLOROETHANE           |
| 316.         | ETHANEDIAMINE                        | ETHYLENEDIAMINE             |

| <u>INDEX</u> | <u>SYNONYM</u>            | <u>CHEMICAL NAME</u>  |
|--------------|---------------------------|-----------------------|
| 317.         | ETHANEDINITRILE           | CYANOGEN              |
| 318.         | ETHANEDIOIC ACID          | OXALIC ACID           |
| 319.         | ETHANENITRILE             | ACETONITRILE          |
| 320.         | ETHANETHIOL               | ETHYL MERCAPTAN       |
| 321.         | ETHANOIC ACID             | ACETIC ACID           |
| 322.         | ETHANOIC ANHYDRIDE        | ACETIC ANHYDRIDE      |
| 323.         | ETHANOLAMINE              | MONOETHANOLAMINE      |
| 324.         | ETHER                     | DIETHYL ETHER         |
| 325.         | ETHER CYANATUS            | PROPIONITRILE         |
| 326.         | ETHER HYDROCHLORIC        | ETHYL CHLORIDE        |
| 327.         | ETHOXYCARBONYLETHYLENE    | ETHYL ACRYLATE        |
| 328.         | ETHYL 2-PROPENOATE        | ETHYL ACRYLATE        |
| 329.         | ETHYL ACETATE             | ETHYL ACETATE         |
| 330.         | ETHYL ACETONE             | METHYL PROPYL KETONE  |
| 331.         | ETHYL ACRYLATE            | ETHYL ACRYLATE        |
| 332.         | ETHYL BROMIDE             | ETHYL BROMIDE         |
| 333.         | ETHYL BUTANOATE           | ETHYL BUTYRATE        |
| 334.         | ETHYL BUTYL ETHER         | ETHYL BUTYL ETHER     |
| 335.         | ETHYL BUTYRATE            | ETHYL BUTYRATE        |
| 336.         | ETHYL CHLOROACETATE       | ETHYL CHLOROACETATE   |
| 337.         | ETHYL CHLOROCARBONATE     | ETHYL CHLOROFORMATE   |
| 338.         | ETHYL CHLOROETHANOATE     | ETHYL CHLOROACETATE   |
| 339.         | ETHYL CHLOROFORMATE       | ETHYL CHLOROFORMATE   |
| 340.         | ETHYL CYANIDE             | PROPIONITRILE         |
| 341.         | ETHYL ETHER               | DIETHYL ETHER         |
| 342.         | ETHYL FORMATE             | ETHYL FORMATE         |
| 343.         | ETHYL FORMIC ESTER        | ETHYL FORMATE         |
| 344.         | ETHYL HYDROSULPHIDE       | ETHYL MERCAPTAN       |
| 345.         | ETHYL MERCAPTAN           | ETHYL MERCAPTAN       |
| 346.         | ETHYL METHACRYLATE        | ETHYL METHACRYLATE    |
| 347.         | ETHYL METHYL KETONE       | ETHYL METHYL KETONE   |
| 348.         | ETHYL NITRATE             | NITRIC ETHER          |
| 349.         | ETHYL PROPENOATE          | ETHYL ACRYLATE        |
| 350.         | ETHYL SILICON TRICHLORIDE | ETHYL TRICHLOROSILANE |
| 351.         | ETHYL SULPHYDRATE         | ETHYL MERCAPTAN       |
| 352.         | ETHYL SULPHIDE            | DIETHYL SULPHIDE      |

| <u>INDEX</u> | <u>SYNONYM</u>              | <u>CHEMICAL NAME</u>      |
|--------------|-----------------------------|---------------------------|
| 353.         | ETHYL THIOALCOHOL           | ETHYL THIOALCOHOL         |
| 354.         | ETHYL n-BUTYRATE            | ETHYL BUTYRATE            |
| 355.         | ETHYL-2-METHYL-2-PROPENOATE | ETHYL METHACRYLATE        |
| 356.         | ETHYL-2-METHYLACRYLATE      | ETHYL METHACRYLATE        |
| 357.         | ETHYLAMINE                  | ETHYLAMINE                |
| 358.         | ETHYLBENZENE                | ETHYLBENZENE              |
| 359.         | ETHYLBENZOL                 | ETHYLBENZENE              |
| 360.         | ETHYL CARBINOL              | n-PROPYL ALCOHOL          |
| 361.         | ETHYL CHLORIDE              | ETHYL CHLORIDE            |
| 362.         | ETHYLDICHLOROARSINE         | ETHYLDICHLOROARSINE       |
| 363.         | ETHYLENE ALDEHYDE           | ACROLEIN                  |
| 364.         | ETHYLENE BROMIDE            | ETHYLENE DIBROMIDE        |
| 365.         | ETHYLENE CHLORIDE           | ETHYLENE DICHLORIDE       |
| 366.         | ETHYLENE CHLOROHYDRIN       | ETHYLENE CHLOROHYDRIN     |
| 367.         | ETHYLENE DIBROMIDE          | ETHYLENE DIBROMIDE        |
| 368.         | ETHYLENE DICHLORIDE         | ETHYLENE DICHLORIDE       |
| 369.         | ETHYLENE OXIDE              | ETHYLENE OXIDE            |
| 370.         | ETHYLENE TETRACHLORIDE      | PERCHLOROETHYLENE         |
| 371.         | ETHYLENE TRICHLORIDE        | TRICHLOROETHYLENE         |
| 372.         | ETHYLENEDIAMINE             | ETHYLENEDIAMINE           |
| 373.         | ETHYLENEIMINE               | ETHYLENEIMINE             |
| 374.         | ETHYLFORMIC ACID            | PROPIONIC ACID            |
| 375.         | ETHYLIDENE CHLORIDE         | DICHLOROETHANE            |
| 376.         | ETHYLMETHANOATE             | ETHYL FORMATE             |
| 377.         | ETHYLTRICHLOROSILANE        | ETHYLTRICHLOROSILANE      |
| 378.         | FC 114                      | DICHLOROTETRAFLUOROETHANE |
| 379.         | FC 22                       | CHLORODIFLUOROMETHANE     |
| 380.         | FERTILIZER ACID             | SULPHURIC ACID            |
| 381.         | FLUORHYDRIC ACID            | HYDROFLUORIC ACID         |
| 382.         | FLUORINE                    | FLUORINE                  |
| 383.         | FLUOROCARBON 114            | DICHLOROTETRAFLUOROETHANE |
| 384.         | FLUOROCARBON 22             | CHLORODIFLUOROMETHANE     |
| 385.         | FLUORODICHLOROMETHANE       | DICHLOROFLUOROMETHANE     |
| 386.         | FLUOROETHENE                | VINYL FLUORIDE            |
| 387.         | FLUOROETHYLENE              | VINYL FLUORIDE            |
| 388.         | FORMAL                      | METHYLAL                  |

| <u>INDEX</u> | <u>SYNONYM</u>              | <u>CHEMICAL NAME</u>      |
|--------------|-----------------------------|---------------------------|
| 389.         | FORMALDEHYDE                | FORMALDEHYDE              |
| 390.         | FORMALDEHYDE DIMETHYLACETAL | METHYLAL                  |
| 391.         | FORMALDEHYDE POLYMER        | PARAFORMALDEHYDE          |
| 392.         | FORMALIN                    | FORMALDEHYDE              |
| 393.         | FORMALITH                   | FORMALDEHYDE              |
| 394.         | FORMIC ACID                 | FORMIC ACID               |
| 395.         | FORMIC ACID ALLYL ESTER     | ALLYL FORMATE             |
| 396.         | FORMIC ACID ETHYL ESTER     | ETHYL FORMATE             |
| 397.         | FORMIC ACID METHYL ESTER    | METHYL FORMATE            |
| 398.         | FORMIC ALDEHYDE             | FORMALDEHYDE              |
| 399.         | FORMYLIC ACID               | FORMIC ACID               |
| 400.         | FREON 114                   | DICHLOROTETRAFLUOROETHANE |
| 401.         | FREON 115                   | CHLOROPENTAFLUOROETHANE   |
| 402.         | FREON 12                    | DICHLORODIFLUOROMETHANE   |
| 403.         | FREON 21                    | DICHLOROFLUOROMETHANE     |
| 404.         | FREON 22                    | CHLORODIFLUOROMETHANE     |
| 405.         | FURAL                       | FURFURAL                  |
| 406.         | FURAN                       | FURAN                     |
| 407.         | 2-FURANCARBINOL             | FURFURYL ALCOHOL          |
| 408.         | 2,5-FURANEDIONE             | MALEIC ANHYDRIDE          |
| 409.         | FURFURAL                    | FURFURAL                  |
| 410.         | FURFURALCOHOL               | FURFURYL ALCOHOL          |
| 411.         | FURFURALDEHYDE              | FURFURAL                  |
| 412.         | FURFURYL ALCOHOL            | FURFURYL ALCOHOL          |
| 413.         | 2-FURYL-METHANOL            | FURFURYL ALCOHOL          |
| 414.         | FYDE                        | FORMALDEHYDE              |
| 415.         | GAMMA-CHLOROALLYL CHLORIDE  | DICHLOROPROPENE           |
| 416.         | GERMANE                     | GERMANE                   |
| 417.         | GERMANIUM HYDRIDE           | GERMANE                   |
| 418.         | GERMANIUM TETRAHYDRIDE      | GERMANE                   |
| 419.         | GLACIAL ACETIC ACID         | ACETIC ACID               |
| 420.         | GLYCOL CHLOROHYDRIN         | ETHYLENE CHLOROHYDRIN     |
| 421.         | GLYCOL ETHYLENE ETHER       | DIOXANE                   |
| 422.         | GLYCOMONOCHELOROHYDRIN      | ETHYLENE CHLOROHYDRIN     |
| 423.         | GUM CAMPHOR                 | CAMPHOR                   |
| 424.         | HALON 2001                  | ETHYL BROMIDE             |

| <u>INDEX</u> | <u>SYNONYM</u>               | <u>CHEMICAL NAME</u>        |
|--------------|------------------------------|-----------------------------|
| 425.         | HALON 242                    | DICHLOROTETRAFLUROETHANE    |
| 426.         | HCCPD                        | HEXACHLOROCYCLOPENTADIENE   |
| 427.         | HEPTANE                      | HEPTANE                     |
| 428.         | HEPTANONE                    | CAMPHOR                     |
| 429.         | HEPTYL HYDRIDE               | HEPTANE                     |
| 430.         | HEXACHLOROBUTADIENE          | HEXACHLOROBUTADIENE         |
| 431.         | HEXACHLOROCYCLOPENTADIENE    | HEXACHLOROCYCLOPENTADIENE   |
| 432.         | HEXAFLUROACETONE             | HEXAFLUROACETONE            |
| 433.         | HEXAFLUROPROPENE             | HEXAFLUROPROPYLENE          |
| 434.         | HEXAFLUROPROPYLENE           | HEXAFLUROPROYLENE           |
| 435.         | HEXAHYDROANILINE             | CYCLOHEXYLAMINE             |
| 436.         | HEXAHYDROBENZENE             | CYCLOHEXANE                 |
| 437.         | HEXAMETHYLENE                | CYCLOHEXANE                 |
| 438.         | HEXAMETHYLENEDIAMINE         | HEXAMETHYLENEDIAMINE        |
| 439.         | HEXANAPHTHENE                | CYCLOHEXANE                 |
| 440.         | HEXANE                       | HEXANE                      |
| 441.         | 1,6-HEXANEDIAMINE            | HEXAMETHYLENEDIAMINE        |
| 442.         | HEXONE                       | METHYL ISOBUTYL KETONE      |
| 443.         | HEXYL HYDRIDE                | HEXANE                      |
| 444.         | HYDRAZINE                    | HYDRAZINE                   |
| 445.         | HYDRAZINE ANHYDROUS          | HYDRAZINE                   |
| 446.         | HYDRAZINE BASE               | HYDRAZINE                   |
| 447.         | HYDRAZOMETHANE               | METHYLHYDRAZINE             |
| 448.         | HYDROBROMIC ACID             | HYDROGEN BROMIDE            |
| 449.         | HYDROCHLORIC ACID            | HYDROCHLORIC ACID           |
| 450.         | HYDROCHLORIC ACID ANHYDROUS  | HYDROGEN CHLORIDE ANHYDROUS |
| 451.         | HYDROCYANIC ACID             | HYDROGEN CYANIDE            |
| 452.         | HYDROCYANIC ACID SODIUM SALT | SODIUM CYANIDE              |
| 453.         | HYDROCYANIC ETHER            | PROPIONITRILE               |
| 454.         | HYDROFLUORIC ACID            | HYDROFLUORIC ACID           |
| 455.         | HYDROFLUORIC ACID ANHYDROUS  | HYDROGEN FLUORIDE           |
| 456.         | HYDROFLUORIC ACID AQUEOUS    | HYDROFLUORIC ACID           |
| 457.         | HYDROGEN ANTIMONIDE          | STIBINE                     |
| 458.         | HYDROGEN BROMIDE             | HYDROGEN BROMIDE            |
| 459.         | HYDROGEN CHLORIDE ANHYDROUS  | HYDROGEN CHLORIDE           |
| 460.         | HYDROGEN CYANIDE             | HYDROGEN CYANIDE            |
| 461.         | HYDROGEN DIOXIDE             | HYDROGEN PEROXIDE           |

| <u>INDEX</u> | <u>SYNONYM</u>              | <u>CHEMICAL NAME</u>     |
|--------------|-----------------------------|--------------------------|
| 462.         | HYDROGEN FLUORIDE           | HYDROGEN FLUORIDE        |
| 463.         | HYDROGEN PEROXIDE           | HYDROGEN PEROXIDE        |
| 464.         | HYDROGEN PHOSPHIDE          | PHOSPHINE                |
| 465.         | HYDROGEN SELENIDE           | HYDROGEN SELENIDE        |
| 466.         | HYDROGEN SULPHIDE           | HDYROGEN SULPHIDE        |
| 467.         | HYDROXYBENZENE              | PHENOL                   |
| 468.         | 2-HYDROXYETHYLAMINE         | MONOETHANOLAMINE         |
| 469.         | 2-HYDROXYETHYLFURAN         | FURFURYL ALCOHOL         |
| 470.         | HYDROXYTOLUENES             | CRESOLS                  |
| 471.         | HYLENE T                    | TOLUENE-2,4-DIISOCYANATE |
| 472.         | IODOMETHANE                 | METHYL IODIDE            |
| 473.         | IRON CARBONYL               | IRON PENTACARBONYL       |
| 474.         | IRON PENTACARBONYL          | IRON PENTACARBONYL       |
| 475.         | ISO CYANATOMETHANE          | METHYL ISOCYANATE        |
| 476.         | ISOBUTENE                   | ISOBUTYLENE              |
| 477.         | ISOBYTYL METHYL KETONE      | METHYL ISOBUTYL KEYTONE  |
| 478.         | ISOBYUTYLENE                | ISOBUTYLENE              |
| 479.         | ISOBUTYRIC ACID             | ISOBUTYRIC ACID          |
| 480.         | ISOBUTYRONITRILE            | ISOBUTYRONITRILE         |
| 481.         | ISOCYANATOBENZENE           | PHENYL ISOCYANATE        |
| 482.         | ISOCYANIC ACID              | METHYL ISOCYANATE        |
| 483.         | ISOCYANIC ACID PROPYL ESTER | PROPYL ISOCYANATE        |
| 484.         | ISOPROPANETHIOL             | ISOPROPANETHIOL          |
| 485.         | ISOPROPYL ACETATE           | ISOPROPYL ACETATE        |
| 486.         | ISOPROPYL BENZENE           | ISOPROPYL BENZENE        |
| 487.         | ISOPROPYL BORATE            | TRIISOPROPYL BORATE      |
| 488.         | ISOPROPYL CHLOROCARBONATE   | ISOPROPYL CHLOROFORMATE  |
| 489.         | ISOPROPYL CHLOROFORMATE     | ISOPROPYL CHLOROFORMATE  |
| 490.         | ISOPROPYL CHLOROMETHANOATE  | ISOPROPYL CHLOROFORMATE  |
| 491.         | ISOPROPYL CYANIDE           | ISOBUTYRONITRILE         |
| 492.         | ISOPROPYL ETHER             | DIISOPROPYL ETHER        |
| 493.         | ISOPROPYL MERCAPTAN         | ISOPROPANETHIOL          |
| 494.         | ISOPROPYLACETONE            | METHYL ISOBUTYL KETONE   |
| 495.         | ISOPROPYLAMINE              | ISOPROPYLAMINE           |
| 496.         | ISOPROPYLTHIOL              | ISOPROPYTHIOL            |
| 497.         | KETONE PROPANE              | ACETONE                  |
| 498.         | LAUREL CAMPHOR              | CAMPHOR                  |

| <u>INDEX</u> | <u>SYNONYM</u>                | <u>CHEMICAL NAME</u>        |
|--------------|-------------------------------|-----------------------------|
| 499.         | LEAD TETRAETHYL               | TETRAETHYL LEAD             |
| 500.         | LEAD TETRAMETHYL              | TETRAMETHYL LEAD            |
| 501.         | LEVOXINE                      | HYDRAZINE                   |
| 502.         | LIQUID AMMONIA                | AMMONIA ANHYDROUS           |
| 503.         | MALEIC ANHYDRIDE              | MALEIC ANHYDRIDE            |
| 504.         | MDI                           | DIPHENYLMETHANEDIISOCYANATE |
| 505.         | MEK                           | ETHYL METHYL KETONE         |
| 506.         | MERCAPTOETHANE                | EHTYL MERCAPTAN             |
| 507.         | MERCAPTOMETHANE               | METHYL MERCAPTAN            |
| 508.         | MERCURIALIN                   | METHYLAMINE                 |
| 509.         | METHACETONE                   | DIETHYL KETONE              |
| 510.         | METHACRYLALDEHYDE             | METHACRYLALDEHYDE           |
| 511.         | METHACRYLIC ACID METHYL ESTER | METHYL METHACRYLATE         |
| 512.         | METHANAL                      | FORMALDEHYDE                |
| 513.         | METHANE TETRABROMIDE          | TETRABROMOETHANE            |
| 514.         | METHANESULFENIC ACID          | PERCHLOROMETHYLMERCAPTAN    |
| 515.         | METHANETHIOL                  | METHYL MERCAPTAN            |
| 516.         | METHANOIC ACID                | FORMIC ACID                 |
| 517.         | METHENYL TRIBROMIDE           | BROMOFORM                   |
| 518.         | METHOXYANILINE                | ANSIDINE                    |
| 519.         | METHOXYETHENE                 | VINYL METHYL ETHER          |
| 520.         | METHOXYETHYLENE               | VINYL METHYL ETHER          |
| 521.         | METHOXYPHENYLAMINE            | ANSIDINE                    |
| 522.         | METHYL ACETATE                | METHYL ACETATE              |
| 523.         | METHYL AZIRIDINE              | PROPYLENEIMINE              |
| 524.         | METHYL BROMIDE                | METHYL BROMIDE              |
| 525.         | METHYL CHLOROCARBONATE        | METHYL CHLOROFORMATE        |
| 526.         | METHYL CHLOROFORMATE          | METHYL CHLOROFORMATE        |
| 527.         | METHYL ETHANOATE              | METHYL ACETATE              |
| 528.         | METHYL ETHER                  | DIMETHYL ETHER              |
| 529.         | METHYL ETHYL KETONE           | ETHYL METHYL KETONE         |
| 530.         | METHYL FORMATE                | METHYL FORMATE              |
| 531.         | METHYL IODIDE                 | METHYL IODIDE               |
| 532.         | METHYL ISOBUTYL KETONE        | METHYL ISOBUTYL KETONE      |
| 533.         | METHYL ISOCYANATE             | METHYL ISOCYANATE           |
| 534.         | METHYL KETONE                 | ACETONE                     |



| <u>INDEX</u> | <u>SYNONYM</u>              | <u>CHEMICAL NAME</u>  |
|--------------|-----------------------------|-----------------------|
| 535.         | METHYL MERCAPTAN            | METHYL MERCAPTAN      |
| 536.         | METHYL METHACRYLATE         | METHYL METHACRYLATE   |
| 537.         | METHYL METHACRYLATE MONOMER | METHYL METHACRYLATE   |
| 538.         | METHYL NITRITE              | METHYL NITRITE        |
| 539.         | METHYL PARATHION            | METHYL PARATHION      |
| 540.         | METHYL PHOSPHITE            | TRIMETHYLPHOSPHITE    |
| 541.         | METHYL PROPENE              | ISOBUTYLENE           |
| 542.         | METHYL PROPYL KETONE        | METHYL PROPYL KETONE  |
| 543.         | METHYL SULPHYDRATE          | METHYL MERCAPTAN      |
| 544.         | METHYL VINYL ETHER          | VINYL METHYL ETHER    |
| 545.         | METHYL VINYL KETONE         | METHYL VINYL KETONE   |
| 546.         | METHYL-2 PROPIONITIRLE      | ISOBUTYRONITRILE      |
| 547.         | METHYLACETIC ACID           | PROPIONIC ACID        |
| 548.         | METHYLACRYLALDEHYDE         | METHYLACRYLALDEHYDE   |
| 549.         | METHYLAL                    | METHYLAL              |
| 550.         | METHYLAMINE                 | METHYLAMINE           |
| 551.         | METHYLARSINE DICHLORIDE     | METHYL DICHLOROARSINE |
| 552.         | METHYLBENZENE               | TOLUENE               |
| 553.         | METHYLBENZOL                | TOLUENE               |
| 554.         | METHYL CHLORIDE             | METHYL CHLORIDE       |
| 555.         | METHYL CHLOROFORM           | 1,1,1-TRICHLOROETHANE |
| 556.         | METHYL CYANIDE              | ACETONITRILE          |
| 557.         | METHYLDICHLOROARSINE        | METHYLDICHLOROARSINE  |
| 558.         | METHYLENE ACETONE           | METHYL VINYL KETONE   |
| 559.         | METHYLENE CHLORIDE          | DICHLOROMETHANE       |
| 560.         | METHYLENE DICHLORIDE        | DICHLOROMETHANE       |
| 561.         | METHYLENE DIMETHYL ETHER    | METHYLAL              |
| 562.         | METHYLENE OXIDE             | FORMALDEHYDE          |
| 563.         | METHYL OXIRANE              | PROPYLENE OXIDE       |
| 564.         | METHYLEHTYLENEIMINE         | PROPYLENEIMINE        |
| 565.         | METHYLETHYLMETHANE          | BUTANE                |
| 566.         | METHYLHYDRAZINE             | METHYLHYDRAZINE       |
| 567.         | METHYLMETHANAMINE           | DIMETHYLAMINE         |
| 568.         | METHYLPHENOLS               | CRESOLS               |
| 569.         | METHYLPROPANOIC ACID        | ISOBUTYRIC ACID       |
| 570.         | METHYLPROPIONIC ACID        | ISOBUTYRIL ACID       |
| 571.         | MEVINPHOS                   | MEVINPHOS             |

| <u>INDEX</u> | <u>SYNONYM</u>                             | <u>CHEMICAL NAME</u>       |
|--------------|--|----------------------------|
| 572.         | MIC  | METHYL ISOCYANATE          |
| 573.         | MIXTURE OF BENZENE, TOLUENE<br>AND XYLENES | NAPHTHA (COAL TAR)         |
| 574.         | MMH  | METHYLHYDRAZINE            |
| 575.         | MONDUR TDS                                 | TOLUENE-2,4-DIISOCYANATE   |
| 576.         | MONOALLYLAMINE                             | ALLYLAMINE                 |
| 577.         | MONOBROMOETHANE                            | ETHYL BROMIDE              |
| 578.         | MONOCHLOROACETALDEHYDE                     | CHLOROACETALDEHYDE         |
| 579.         | MONOCHLORODIFLUOROMETHANE                  | CHLORODIFLUORMETHANE       |
| 580.         | MONOCHLOROTRIMETHYLSILICON                 | MONOCHLOROTRIMETHYLSILICON |
| 581.         | MONOETHANOLAMINE                           | MONOETHANOLAMINE           |
| 582.         | MONOETHYLAMINE                             | ETHYLAMINE                 |
| 583.         | MONOMETHYLAMINE                            | METHYLAMINE                |
| 584.         | MONOMETHYLHYDRAZINE                        | METHYLHYDRAZINE            |
| 585.         | MONOSILANE                                 | SILANE                     |
| 586.         | MORPHOLINE                                 | MORPHOLINE                 |
| 587.         | MPK  | METHYL PROPYL KETONE       |
| 588.         | MURIATIC ACID                              | HYDROCHLORIC ACID          |
| 589.         | NACCONATE 100                              | TOLUENE-2,4-DIISOCYANATE   |
| 590.         | NAPHTHA (COAL TAR)                         | NAPHTHA (COAL TAR)         |
| 591.         | NAPHTHALENE                                | NAPHTHALENE                |
| 592.         | NAPHTHALINE                                | NAPHTHALENE                |
| 593.         | NICKEL CARBONYL                            | NICKEL CARBONYL            |
| 594.         | NICKEL TETRACARBONYL                       | NICKEL CARBONYL            |
| 595.         | NITRIC ACID                                | NITRIC ACID                |
| 596.         | NITRIC ETHER                               | NITRIC ETHER               |
| 597.         | NITRIC OXIDE                               | NITRIC OXIDE               |
| 598.         | NITRITO                                    | NITROGEN DIOXIDE           |
| 599.         | NITROCARBOL                                | NITROMETHANE               |
| 600.         | NITROCHLOROFORM                            | CHLOROPICRINE              |
| 601.         | NITROETHANE                                | NITROETHANE                |
| 602.         | NITROGEN DIOXIDE                           | NITROGEN DIOXIDE           |
| 603.         | NITROGEN MONOXIDE                          | NITRIC OXIDE               |
| 604.         | NITROGEN PEROXIDE                          | NITROGEN DIOXIDE           |
| 605.         | NITROGEN TETROXIDE                         | NITROGEN DIOXIDE           |
| 606.         | NITROGEN TRIFLUORIDE                       | NITROGEN TRIFLUORIDE       |

| <u>INDEX</u> | <u>SYNONYM</u>            | <u>CHEMICAL NAME</u>      |
|--------------|---------------------------|---------------------------|
| 607.         | NITROMETHANE              | NITROMETHANE              |
| 608.         | NITROPROPANE              | NITROPROPANE              |
| 609.         | NITROTRICHLOROMETHANE     | CHLOROPICRINE             |
| 610.         | NITROUS ACID METHYL ESTER | METHYL NITRATE            |
| 611.         | NONANE                    | NONANE                    |
| 612.         | OCTAFLUOROBUT-2-ENE       | OCTAFLUOROBUT-2-ENE       |
| 613.         | OIL OF VITRIOL            | SULPHURIC ACID            |
| 614.         | ORTHOARSENIC ACID         | ARSENIC ACID              |
| 615.         | ORVINYLCARBINOL           | ALLYLALCOHOL              |
| 616.         | OXALONITRILE              | CYANOGEN                  |
| 617.         | 2-OXOHEXAMETHYLENIMINE    | CAPROLACTAM               |
| 618.         | ORTHOPHOSPHORIC ACID      | PHOSPHORIC ACID           |
| 619.         | OXALIC ACID               | OXALIC ACID               |
| 620.         | OXIRANE                   | ETHYLENE OXIDE            |
| 621.         | OXYDE DE CARBONE          | CARBON MONOXIDE           |
| 622.         | OXYTOLUENES               | CRESOLS                   |
| 623.         | PARADI                    | p-DICHLOROBENZENE         |
| 624.         | PARACHLOROBENZENE         | p-DICHLOROBENZENE         |
| 625.         | PARADOW                   | p-DICHLOROBENZENE         |
| 626.         | PARAFORM                  | PARAFORMALDEHYDE          |
| 627.         | PARAFORMALDEHYDE          | PARAFORMALDEHYDE          |
| 628.         | PCB                       | POLYCHLORINATED BIPHENYL  |
| 629.         | PCL                       | HEXACHLOROCYCLOPENTADIENE |
| 630.         | PCM                       | PERCHLOROMETHYLMERCAPTAN  |
| 631.         | PCP                       | PENTACHLOROPHENOL         |
| 632.         | PENTA                     | PENTACHLOROPHENOL         |
| 633.         | PENTABORANE               | PENTABORANE               |
| 634.         | PENTABORON NONAHYDRIDE    | PENTABORANE               |
| 635.         | PENTACARBONYLIRON         | IRON PENTACARBONYL        |
| 636.         | PENTACHLOROETHANE         | PENTACHLOROETHANE         |
| 637.         | PENTACHLOROPHENOL         | PENTACHLOROPHENOL         |
| 638.         | PENTAFLUORIDE             | ANTIMONY PENTAFLUORIDE    |
| 639.         | PENTAFLUOROANTIMONY       | ANTIMONY PENTAFLUORIDE    |
| 640.         | PENTALIN                  | PENTACHLOROETHANE         |
| 641.         | PENTANAL                  | VALERALDEHYDE             |
| 642.         | PENTANE                   | PENTANE                   |

| <u>INDEX</u> | <u>SYNONYM</u>                   | <u>CHEMICAL NAME</u>                 |
|--------------|----------------------------------|--------------------------------------|
| 643.         | 1-PENTANOL                       | n-AMYL ALCOHOL                       |
| 644.         | PENTYL ALCOHOL                   | n-AMYL ALCOHOL                       |
| 645.         | PERCHLOROBUTADIENE               | HEXACHLOROBUTADIENE                  |
| 646.         | PERCHLOROCYCLOPENTADIENE         | HEXACHLOROCYCLOPENTADIENE            |
| 647.         | PERCHLOROETHYLENE                | PERCHLOROETHYLENE                    |
| 648.         | PERCHLOROMETHYLMERCAPTAN         | PERCHLOROMETHYLMERCAPTAN             |
| 649.         | PERCLEN                          | PERCHLOROETHYLENE                    |
| 650.         | PERFLUORO-2-BUTENE               | OCTAFLUOROBUT-2-ENE                  |
| 651.         | PERFLUOROETHENE                  | TETRAFLUOROETHENE                    |
| 652.         | PERFLUOROETHYLENE                | TETRAFLUOROETHENE                    |
| 653.         | PERFLUOROPROPENE                 | HEXAFLUOROPROPYLENE                  |
| 654.         | PERFLUOROPROPYLENE               | HEXAFLUOROPROPYLENE                  |
| 655.         | PEROXIDE                         | HYDROGEN PEROXIDE                    |
| 656.         | PHENOL                           | PHENOL                               |
| 657.         | PHENOXY PESTICIDES               | 2,4-DICHLOROPHENOXYACETIC ACID       |
| 658.         | PHENYL CARBONIMIDE               | PHENYL ISOCYANATE                    |
| 659.         | PHENYL ISOCYANATE                | PHENYL ISOCYANATE                    |
| 660.         | PHENYLCARBIMIDE                  | PHENYL ISOCYANATE                    |
| 661.         | PHENYLMERCAPTAN                  | PHENYLMERCAPTAN                      |
| 662.         | PHOSDRIN                         | MEVINPHOS                            |
| 663.         | PHOSGENE                         | PHOSGENE                             |
| 664.         | PHOSPHINE                        | PHOSPHINE                            |
| 665.         | PHOSPHORIC ACID TRIETHYLENEIMIDE | TRI-(1-AZIRIDINYL)PHOSPHINE<br>OXIDE |
| 666.         | PHOSPHORIC ACID TRIETHYLENEIMINE | TRI-(1-AZIRIDINYL)PHOSPHINE<br>OXIDE |
| 667.         | PHOSPHORUS CHLORIDE              | PHOSPHORUS CHLORIDE                  |
| 668.         | PHOSPHORUS OXYCHLORIDE           | PHOSPHORUS OXYCHLORIDE               |
| 669.         | PHOSPHORUS TRICHLORIDE           | PHOSPHORUS TRICHLORIDE               |
| 670.         | PHENYLAMINE                      | ANILINE                              |
| 671.         | n-PHENYLANILINE                  | DIPHENYLAMINE                        |
| 672.         | PHENYLETHANE                     | ETHYLBENZENE                         |
| 673.         | PHENYLMETHANE                    | TOLUENE                              |
| 674.         | PHOSPHORIC ACID                  | PHOSPHORIC ACID                      |
| 675.         | PHOSPHORUS                       | PHOSPHORUS                           |
| 676.         | PHOSPHORUS WHITE                 | PHOSPHORUS                           |

| <u>INDEX</u> | <u>SYNONYM</u>           | <u>CHEMICAL NAME</u>     |
|--------------|--------------------------|--------------------------|
| 677.         | POLYCHLORINATED BIPHENYL | POLYCHLORINATED BIPHENYL |
| 678.         | POLYCHLOROCAMPHENE       | TOXAPHENE                |
| 679.         | POLYFORMALDEHYDE         | PARAFORMALDEHYDE         |
| 680.         | POLYOXYMETHYLENE         | PARAFORMALDEHYDE         |
| 681.         | PROPALDEHYDE             | PROPIONALDEHYDE          |
| 682.         | PROPANAL                 | PROPIONALDEHYDE          |
| 683.         | PROPANAMINE              | PROPYLAMINE              |
| 684.         | PROPANEITRILE            | PROPIONITRILE            |
| 685.         | 1-PROPANOL               | n-PROPYL ALCOHOL         |
| 686.         | PROPARGYL ALCOHOL        | PROPARGYL ALCOHOL        |
| 687.         | PROPENAL                 | ACROLEIN                 |
| 688.         | PROPENAMIDE 50%          | ACRYLAMIDE               |
| 689.         | PROPENE-3-OL             | ALLYL ALCOHOL            |
| 690.         | 2-PROPENENITRILE         | ACRYLONITRILE            |
| 691.         | PROPENOL                 | ALLYL ALCOHOL            |
| 692.         | PROPENYL ALCOHOL         | ALLYL ALCOHOL            |
| 693.         | PROPENYLAMINE            | ALLYLAMINE               |
| 694.         | PROPIONALDEHYDE          | PROPIONALDEHYDE          |
| 695.         | PROPIONE                 | DIETHYL KETONE           |
| 696.         | PROPIONIC ACID           | PROPIONIC ACID           |
| 697.         | PROPIONIC ALDEHYDE       | PROPIONALDEHYDE          |
| 698.         | PROPIONIC NITRILE        | PROPIONITRILE            |
| 699.         | PROPIONITRILE            | PROPIONITRILE            |
| 700.         | PROPYL ALCOHOL           | n-PROPYL ALCOHOL         |
| 701.         | n-PROPYL ALCOHOL         | n-PROPYL ALCOHOL         |
| 702.         | PROPYL ALDEHYDE          | PROPIONALDEHYDE          |
| 703.         | PROPYL CHLOROCARBONATE   | PROPYL CHLOROFORMATE     |
| 704.         | PROPYLCHLOROFORMATE      | PROPYL CHLOROFORMATE     |
| 705.         | PROPYL CYANIDE           | BUTYRONITRILE            |
| 706.         | PROPYL ISOCYANATE        | PROPYL ISOCYANATE        |
| 707.         | PROPYL NITRATE           | PROPYLNITRATE            |
| 708.         | PROPYLAMINE              | PROPYLAMINE              |
| 709.         | PROPYLENE ALDEHYDE       | CROTONALDEHYDE           |
| 710.         | PROPYLENE CHLOROHYDRIN   | PROPYLENE CHLOROHYDRIN   |
| 711.         | PROPYLENE DICHLORIDE     | PROPYLENE DICHLORIDE     |
| 712.         | PROPYLENE OXIDE          | PROPYLENE OXIDE          |

| <u>INDEX</u> | <u>SYNONYM</u>          | <u>CHEMICAL NAME</u>  |
|--------------|-------------------------|-----------------------|
| 713.         | PROPYLENEIMINE          | PROPYLENEIMINE        |
| 714.         | PROPYLIC ALDEHYDE       | PROPIONALDEHYDE       |
| 715.         | PROPYLNITRILE           | PROPIONITRILE         |
| 716.         | PRUSSIC ACID            | HYDROGEN CYANIDE      |
| 717.         | PYRROLYLENE             | BUTADIENE             |
| 718.         | QUICKLIME               | CALCIUM OXIDE         |
| 719.         | SANTOPHEN 20            | PENTACHLOROPHENOL     |
| 720.         | SEC-PROPYL ACETATE      | ISOPROPYL ACETATE     |
| 721.         | SELANE                  | HYDROGEN SELENIDE     |
| 722.         | SELENINYL CHLORIDE      | SELENIUM OXYCHLORIDE  |
| 723.         | SELENIUM ANHYDRIDE      | HYDROGEN SELENIDE     |
| 724.         | SELENIUM CHLORIDE OXIDE | SELENIUM OXYCHLORIDE  |
| 725.         | SELENIUM FLUORIDE       | SELENIUM HEXAFLUORIDE |
| 726.         | SELENIUM HEXAFLUORIDE   | SELENIUM HEXAFLUORIDE |
| 727.         | SELENIUM HYDRIDE        | HYDROGEN SELENIDE     |
| 728.         | SELENIUM OXYCHLORIDE    | SELENIUM OXYCHLORIDE  |
| 729.         | SILANE                  | SILANE                |
| 730.         | SILICON FLUROIDE        | SILICON TETRAFLUORIDE |
| 731.         | SILICON TETRAFLUROIDE   | SILICON TETRAFLUROIDE |
| 732.         | SILICON TETRAHYDRIDE    | SILANE                |
| 733.         | SKELLYSOLVE B           | HEXANE                |
| 734.         | SODIUM CYANIDE          | SODIUM CYANIDE        |
| 735.         | STIBINE                 | STIBINE               |
| 736.         | STROBANE T              | TOXAPHENE             |
| 737.         | SULPHUR CHLORIDE        | SULPHUR MONOCHLORIDE  |
| 738.         | SULPHUR DIOXIDE         | SULPHUR DIOXIDE       |
| 739.         | SULPHUR FLUORIDE        | SULPHUR HEXAFLUORIDE  |
| 740.         | SULPHUR FLUORIDE        | SULPHUR TETRAFLUORIDE |
| 741.         | SULPHUR HEXAFLUORIDE    | SULPHUR HEXAFLUORIDE  |
| 742.         | SULPHUR TETRAFLUORIDE   | SULPHUR TETRAFLUORIDE |
| 743.         | SULPHURETTED HYDROGEN   | HYDROGEN SULPHIDE     |
| 744.         | SULPHURIC ACID          | SULPHURIC ACID        |
| 745.         | SULPHURIC ACID SPENT    | SULPHURIC ACID        |
| 746.         | SULPHURIC CHLOROHYDRIN  | CHLOROSULPHURIC ACID  |
| 747.         | SULPHUR MONOCHLORIDE    | SULPHUR MONOCHLORIDE  |
| 748.         | SULPHUR SUBCHLORIDE     | SULPHUR MONOCHLORIDE  |

| <u>INDEX</u> | <u>SYNONYM</u>             | <u>CHEMICAL NAME</u>      |
|--------------|----------------------------|---------------------------|
| 749.         | SULPHURIC OXYFLUORIDE      | SULPHURYL FLUORIDE        |
| 750.         | SULPHURYL FLUORIDE         | SULPHURYL FLUORIDE        |
| 751.         | SUPEROXOL                  | HYDROGEN PEROXIDE         |
| 752.         | TAR CAMPHOR                | NAPHTHALENE               |
| 753.         | TDI                        | TOLUENE-2,4-DIISOCYANATE  |
| 754.         | TEL                        | TETRAETHYL LEAD           |
| 755.         | TELLURIUM FLUORIDE         | TELLURIUM HEXAFLUORIDE    |
| 756.         | TELLURIUM HEXAFLUORIDE     | TELLURIUM HEXAFLUORIDE    |
| 757.         | TETRA ALKYL LEAD           | TETRAETHYL LEAD           |
| 758.         | TETRABROMOETHANE           | TETRABROMOETHANE          |
| 759.         | TETRACAP                   | PERCHLOROETHYLENE         |
| 760.         | TETRACARBONYL NICKEL       | NICKEL CARBONYL           |
| 761.         | TETRACHLOROETHANE          | TETRACHLOROETHANE         |
| 762.         | TETRACHLOROETHYLENE        | PERCHLOROETHYLENE         |
| 763.         | TETRACHLOROMETHANE         | CARBON TETRACHLORIDE      |
| 764.         | TETRAETHYL LEAD            | TETRAETHYL LEAD           |
| 765.         | TETRAFLUOROETHENE          | TETRAFLUOROETHENE         |
| 766.         | TETRAFLUOROETHYLENE        | TETRAFLUOROETHENE         |
| 767.         | TETRAFLUOROSULPHURANE      | SULFUR TETRAFLUORIDE      |
| 768.         | TETRAHYDRO-1,4-DIOXIN      | DIOXANE                   |
| 769.         | TETRAHYDRO-p-OXAZINE       | MORPHOLINE                |
| 770.         | TETRAHYDRO-2H-1,4-OXAZINE  | MORPHOLINE                |
| 771.         | TETRAMETHYL LEAD           | TETRAMETHYL LEAD          |
| 772.         | THIOBUTYL ALCOHOL          | BUTYL MERCAPTAN           |
| 773.         | THIOCARBONYL CHLORIDE      | THIOPHOSGENE              |
| 774.         | THIOCARBONYL TETRACHLORIDE | PERCHLOROMETHYL MERCAPTAN |
| 775.         | THIOETHANOL                | ETHYL MERCAPTAN           |
| 776.         | THIOETHYL ALCOHOL          | ETHYL MERCAPTAN           |
| 777.         | THIOETHYL ETHER            | DIETHYL SULFIDE           |
| 778.         | THIOGLYCOL                 | THIOGLYCOL                |
| 779.         | THIOMETHANOL               | METHYL MERCAPTAN          |
| 780.         | THIOMETHYL ALCOHOL         | METHYL MERCAPTAN          |
| 781.         | THIOPHENOL                 | PHENYL MERCAPTAN          |
| 782.         | THIOPHOSGENE               | THIOPHOSGENE              |
| 783.         | TITANIC CHLORIDE           | TITANIUM TETRACHLORIDE    |
| 784.         | TITANIUM TETRACHLORIDE     | TITANIUM TETRACHLORIDE    |

| <u>INDEX</u> | <u>SYNONYM</u>                        | <u>CHEMICAL NAME</u>                 |
|--------------|---------------------------------------|--------------------------------------|
| 785.         | TMA                                   | TRIMETHYL AMINE                      |
| 786.         | TML                                   | TETRAMETHYL LEAD                     |
| 787.         | TOLUENE                               | TOLUENE                              |
| 788.         | 2,4-TOLUENE DIISOCYANATE              | TOLUENE-2,4-DIISOCYANATE             |
| 789.         | TOLUENE-2,4-DIISOCYANATE              | TOLUENE-2,4-DIISOCYANATE             |
| 790.         | TOLUIDINE                             | TOLUIDINE                            |
| 791.         | TOLUOL                                | TOLUENE                              |
| 792.         | TOLYL CHLORIDE                        | BENZYL CHLORIDE                      |
| 793.         | TOPANEL                               | CROTONALDEHYDE                       |
| 794.         | TOXAPHENE                             | TOXAPHENE                            |
| 795.         | TOXILIC ANHYDRIDE                     | MALEIC ANHYDRIDE                     |
| 796.         | TRI-(1-AZIRIDINYL)PHOSPHINE<br>OXIDE  | TRI-(1-AZIRIDINYL)PHOSPHINE<br>OXIDE |
| 797.         | TRIBROMOETHANE                        | BROMOFORM                            |
| 798.         | TRICHOLORBORANE                       | BORON TRICHLORIDE                    |
| 799.         | TRICHLOROBORON                        | BORON TRICHLORIDE                    |
| 800.         | 1,1,1-TRICHLOROETHANE                 | 1,1,1-TRICHLOROETHANE                |
| 801.         | TRICHLOROETHANE                       | 1,1,1-TRICHLOROETHANE                |
| 802.         | TRICHLOROETHENE                       | TRICHLOROETHYLENE                    |
| 803.         | TRICHLOROETHYLENE                     | TRICHLOROETHYLENE                    |
| 804.         | TRICHLOROETHYLSILANE                  | ETHYL TRICHLOROSILANE                |
| 805.         | TRICHLOROETHYLSILICANE                | ETHYL TRICHLOROSILANE                |
| 806.         | TRICHLOROMETHANE                      | CHLOROFORM                           |
| 807.         | TRICHLOROMETHANESULPHENYL<br>CHLORIDE | PERCHLOROMETHYLMERCAPTAN             |
| 808.         | TRICHLORONITROMETHANE                 | CHLOROPICRINE                        |
| 809.         | TRICHLOROPHOSPHINE                    | PHOSPHORUS TRICHLORIDE               |
| 810.         | TRICHLOROPHOSPHINE OXIDE              | PHOSPHORUS OXYCHLORIDE               |
| 811.         | TRICHLOROPHOSPHORUS OXIDE             | PHOSPHORUS OXYCHLORIDE               |
| 812.         | TRICLENE                              | TRICHLOROETHYLENE                    |
| 813.         | TRIFLUOROBORON                        | BORONTRIFLUORIDE                     |
| 814.         | TRIISOPROPYL BORATE                   | TRIISOPROPYL BORATE                  |
| 815.         | TRIMETHOXYPHOSPHINE                   | TRIMETHYLPHOSPHITE                   |
| 816.         | 2,4,4-TRIMETHYL-1-PENTENE             | DIISOBUTYLENE                        |
| 817.         | TRIMETHYLAMINE                        | TRIMETHYLAMINE                       |



| <u>INDEX</u> | <u>SYNONYM</u>         | <u>CHEMICAL NAME</u>   |
|--------------|------------------------|------------------------|
| 818.         | TRIMETHYLCHLOROSILANE  | TRIMETHYLCHLOROSILANE  |
| 819.         | TRIMETHYLPHOSPHITE     | TRIMETHYLPHOSPHITE     |
| 820.         | TRIMETHYLSILY CHLORIDE | TRIMETHYLSILY CHLORIDE |
| 821.         | TRIOXYMETHYLENE        | PARAFORMALDEHYDE       |
| 822.         | TRIPROPYLAMINE         | TRIPROPYLAMINE         |
| 823.         | TROPILIDENE            | CYCLOHEPTATRIENE       |
| 824.         | UDMH                   | DIMETHYL HYDRAZINE     |
| 825.         | UNSLAKED LIME          | CALCIUM OXIDE          |
| 826.         | VALERAL                | VALERALDEHYDE          |
| 827.         | VALERALDEHYDE          | VALERALDEHYDE          |
| 828.         | VALERIC ALDEHYDE       | VALERALDEHYDE          |
| 829.         | VAM                    | VINYL ACETATE          |
| 830.         | VANADIC ANHYDRIDE      | VANADIUM PENTOXIDE     |
| 831.         | VANADIUM PENTAOXIDE    | VANADIUM PENTOXIDE     |
| 832.         | VANADIUM PENTOXIDE     | VANADIUM PENTOXIDE     |
| 833.         | VCL                    | VINYL CHLORIDE         |
| 834.         | VCM                    | VINYL CHLORIDE         |
| 835.         | VINEGAR ACID           | ACETIC ACID            |
| 836.         | VINEGAR NAPHTHA        | ETHYL ACETATE          |
| 837.         | VINYL ACETATE          | VINYL ACETATE          |
| 838.         | VINYL A MONOMER        | VINYL ACETATE          |
| 839.         | VINYL BROMIDE          | VINYL BROMIDE          |
| 840.         | VINYL CHLORIDE         | VINYL CHLORIDE         |
| 841.         | VINYL C MONOMER        | VINYL CHLORIDE         |
| 842.         | VINYL CYANIDE          | ACRYLONITRILE          |
| 843.         | VINYL FLUORIDE         | VINYL FLUORIDE         |
| 844.         | VINYL METHYL ETHER     | VINYL METHYL ETHER     |
| 845.         | VINYLCARBINOL          | ALLYAL ALCOHOL         |
| 846.         | VINYLETHYLENE          | BUTADIENE              |
| 847.         | VINYLDIENE CHLORIDE    | VINYLDIENE CHLORIDE    |
| 848.         | VINYLDIENE DICHLORIDE  | VINYLDIENE CHLORIDE    |
| 849.         | VINYLDINE CHLORIDE     | VINYLDIENE CHLORIDE    |
| 850.         | VYAC                   | VINYL ACETATE          |
| 851.         | WHITE CYANIDE          | SODIUM CYANIDE         |
| 852.         | WHITE PHOSPHORUS       | PHOSPHORUS             |
| 853.         | WOOD ETHER             | DIMETHYL ETHER         |

| <u>INDEX</u> | <u>SYNONYM</u>    | <u>CHEMICAL NAME</u> |
|--------------|-------------------|----------------------|
| 854.         | XYLENES           | XYLENES              |
| 855.         | XYLOLS            | XYLENES              |
| 856.         | YELLOW PHOSPHORUS | PHOSPHORUS           |

II. FIRE HAZARD CODE

1. Flammable.
2. Not flammable.
3. Combustible.
4. Vapour may explode if ignited in an enclosed area.
5. Irritating vapours generated.
6. Poisonous and toxic vapours are produced when heated.
7. Flashback along vapour trail may occur.
8. Vapour is heavier than the air.
9. Toxic oxides of nitrogen may form in fire.
10. Highly flammable liquid.
11. Poisonous gases (Hydrogen Cyanide and Nitrogen Oxides).
12. Presence of oil or other combustible materials increases fire hazard.
13. Emits toxic fumes when heated.
14. Emits toxic fumes on decomposition.
15. Irritating gases generated in fire.
16. Toxic and irritating gases are produced in fire.
17. Containers may explode in fire.
18. Can react with oxidizing material.
19. May cause fire on contact with water and combustibles.
20. Decomposes to carbon monoxide and hydrogen cyanide in fire.
21. Toxic gases are generated.
22. Poisonous and irritating phosgene, chloride and hydrogen chloride gases are produced in fire.
23. May ignite on contact with air.
24. Flammable toxic vapours and poisonous gases are generated in fire.
25. Vapour forms explosive mixture with air.
26. Emits highly toxic fumes when heated to decomposition.
27. Toxic and irritating phosgene gas produced in fire.
28. If mixed with air in critical proportions and in presence of a source of fire, it ignites.
29. Reacts vigorously with metals such as aluminum and magnesium.
30. Toxic and irritating hydrogen chloride and phosgene gases are produced in fire.

31. Irritating vapours are produced when heated.
32. Toxic vapours are generated.
33. Toxic vapours are generated in fire.
34. Flammable gas may be produced on contact with metal.
35. Toxic and irritating chloride vapour produced when heated.
36. Toxic and irritating fluoride vapour produced when heated.
37. Flammable and explosive hydrogen gas produced on contact with metals.
38. Pressurized container explodes and releases toxic and irritating vapours.
39. Causes fire and explodes on contact with combustibles and metals.
40. Toxic oxides of sulphur produced in fire.
41. Dust cloud may be ignited by spark or flames, generating heat and toxic fumes.
42. Toxic and irritating fumes of nitrogen oxides produced when heated.
43. Black smoke, toxic fumes and gases including oxides of carbon and nitrogen are produced when burning in air.
44. Releases flammable and toxic formaldehyde vapours.
45. When heated, forms formaldehyde gas and oxides of carbon.
46. Poisonous gases produced in fire.
47. Poisonous and irritating gases of oxides of phosphorous are produced in fire - forms intense white smoke.
48. Releases highly hazardous cyanides when heated to decomposition or on contact with acid or acid fumes.
49. Container may rupture and release toxic and irritating sulphur dioxide.
50. Toxic and corrosive fumes of chloride and sulphur oxide are produced when heated.
51. Highly toxic fumes of lead produced in fire.
52. Reacts vigorously with oxidizing material.
53. Will increase intensity of fire when in contact with combustibles.
54. Toxic gases of hydrogen chloride, phosgene and carbon monoxide produced in fire.

III. REFERENCES

- Canada Gazette Part II (1985). REGULATIONS RESPECTING THE HANDLING, OFFERING FOR TRANSPORT AND TRANSPORTING OF DANGEROUS GOODS. February.
- Castellan, G.W.  
PHYSICAL CHEMISTRY, Second Edition.  
Addison Wesley Publishing Company, Reading, Mass., 1971.
- Chong, J.  
HAZARDOUS GAS RELEASE MODEL;  
Air Resources Branch, Program documentation, August 1980.
- Eidsvik, K. J.  
A MODEL FOR HEAVY GAS DISPERSION IN THE ATMOSPHERE;  
Atmospheric Environment, 14 769-777 (1980).
- Environmental Canada (1984). MANUAL FOR SPILLS OF HAZARDOUS MATERIALS. Technical Services Branch, Environmental Protection Service.
- Fryer, L.S. and G.D. Kaiser  
DENZ - A COMPUTER PROGRAM FOR THE CALCULATION OF THE DISPERSION OF DENSE TOXIC OR EXPLOSIVE GASES IN THE ATMOSPHERE;  
United Kingdom Atomic Energy Authority, Report SRD R152, 1979.
- Kaiser, G. D. and B. C. Walker  
RELEASE OF ANHYDROUS AMMONIA FROM PRESSURIZED CONTAINERS - THE IMPORTANCE OF DENSER-THAN-AIR MIXTURES;  
Atmospheric Environment, 12 2289-2300 (1978).
- Ontario Ministry of Labour, Regulation 654/86, REGULATION RESPECTING CONTROL OF EXPOSURE TO BIOLOGICAL OR CHEMICAL AGENTS MADE UNDER THE OCCUPATIONAL HEALTH AND SAFETY ACT.
- Ontario Ministry of the Environment (1981). ATMOSPHERIC MONITORING FOR TRANSPORTATION EMERGENCIES. Volume 1.
- Reid, J.  
DISPERSION OF DENSER-THAN-AIR GASES;  
Atmospheric Environment Service, Boundary Layer Research Division, January 1980.
- Rooney, D.R. and E.P. Loi  
AUGMENTATION OF LIST OF TOXIC CHEMICALS;  
Concord Scientific Report, CSC J1108, June 1987.
- Stiver, W. and D. MacKay  
SPILL TECHNOLOGY NEWSLETTER, Jan.-Feb. 1982.

U.S. EPA. CHEMICAL EMERGENCY PREPAREDNESS PROGRAM - INTERIM GUIDELINE  
- CHEMICAL PROFILES. December 1985.

United States Environmental Protection Agency (1985). CHEMICAL  
EMERGENCY PREPAREDNESS PROGRAM INTERIM GUIDELINE. Rev. 1,  
9223.0-1A, November.

Van Ulden, A.P.  
ON THE SPREADING OF A HEAVY GAS RELEASED NEAR THE GROUND;  
First Int. Loss Prevention Symp., The Hague/Delft Elsevier,  
Amsterdam, pp.221-226.

Van Volkenburgh, G., A. Venkatram and J. Reid  
DISPERSION OF HEAVY GASES AND VAPOURS, AND OF INSTANTANEOUS  
RELEASE OF TOXIC GASES. Air Resources Branch Report  
ARB-TDA-31-80, April 1980.

IV. DATA SOURCES

1. ACGIH, TLVs for Chemical Substances in Work Air, 1982.
2. American Conference of Governmental Industrial Hygienists (1986-87). "Threshold Limit Values for Chemical Substances in the Work Environment Adopted by ACGIH." Cincinnati, Ohio.
3. Bretherick, L. Handbook of Reactive Chemical Hazards, 2nd ed. Butterworths, 1979.
4. CRC Handbook of Chemistry and Physics. 65th Edition, CRC Press, Boca Raton, Fl., 1984.
5. CRC Press, Inc. Boca Raton, Florida: Handbook of Chemistry and Physics. 62nd Edition. 1981-1982.
6. Chemical Engineers Handbook. Perry, R.H. and Chilton, C.H. (1973). 5th Edition. McGraw Hill.
7. CHEMINFO (Chemical Information) Data Base. CCOHS/CCHST, 250 Main St. E., Hamilton, Ontario, L8N 1H6.
8. Environment Canada, Technical Information for Problem Spills (TIPS manual), 1981 draft.
9. Ministry of the Environment (1976). "Hazardous Substance Programme, Hazardous Substances List and Handbook." Report Number ARB-TDA-33-76 (revised).
10. NIOSH/OSHA Pocket Guide to Chemical Hazards, 1978.
11. Ontario Ministry of the Environment: Atmospheric Monitoring for Transportation Emergencies. Volume II. Toxic Substance Monitoring and Safety Handbook. August 1981. Report No. ARB-030-81.
12. Sax, N.I. Dangerous Properties of Industrial Materials, 5th ed. Van Nostrand Reinhold Co., 1979.
13. Tatken, R.L. and Lewis, R.J. (1983). Registry of Toxic Effects of Chemical Substances." U.S. Dept. of Health and Human Services, Public Health Service Centre for Disease Control, NIOSH, Cincinnati, Ohio, 45226.
14. The Van Nostrand Reinhold Co., revised by Gressner G. Hawley: The Condensed Chemical Dictionary. 10th Edition.
15. Weiss, G., editor: Hazardous Chemical Data Book, Noyes Data Corp., 1980.